

ViewDS Access Presence: Technical Reference Guide

Published: November 2024 Version: 7.5.2 © ViewDS Identity Solutions

ViewDS Access Presence: Technical Reference Guide

For ViewDS Directory release 7.5.2 November 2024

Document Lifecycle

ViewDS may occasionally update documentation between software releases. Therefore, please visit www.viewds.com to ensure you have the PDF with most recent publication date. The site also hosts the most recent version of this document in HTML format.

This publication is copyright. Other than for the purposes of and subject to the conditions prescribed under the Copyright Act, no part of it may in any form or by any means (electronic, mechanical, microcopying, photocopying, recording or otherwise) be reproduced, stored in a retrieval system or transmitted without prior written permission. Inquiries should be addressed to the publishers.

The contents of this publication are subject to change without notice. All efforts have been made to ensure the accuracy of this publication. Notwithstanding, ViewDS Identity Solutions does not assume responsibility for any errors nor for any consequences arising from any errors in this publication.

The software and/or databases described in this document are furnished under a licence agreement. The software and/or databases may be used or copied only in accordance with the terms of the agreement.

ViewDS Directory, ViewDS Access Presence and ViewDS Access Sentinel are trademarks of ViewDS Identity Solutions. Microsoft is a registered trademark and Windows is a trademark of Microsoft Corporation. All other product and company names are trademarks or registered trademarks of their respective holders.

Copyright © 1995-2024 ViewDS Identity Solutions ABN 19 092 422 47

Contents

Chapter 1: About this guide	1
Who should read this guide	1
Conventions	1
Related documents	2
How this guide is organized	2
Chapter 2: System overview	5
Overview of Access Presence	5
Overview of the Printing DUA	11
Chapter 3: Configuration files	13
Access Presence configuration files	13
ViewDS configuration file	18
Additional Access Presence files	29
Configuring for printing	29
Configuring for global changes	
Chapter 4: Templates and tags	
Common tags and arguments	
Common tags and arguments	32 33
Common tags and arguments	
Common tags and arguments Authentication template Two-factor authentication templates	
Common tags and arguments Authentication template Two-factor authentication templates Welcome template	
Common tags and arguments Authentication template Two-factor authentication templates Welcome template Search Forms template	
Common tags and arguments Authentication template Two-factor authentication templates Welcome template Search Forms template Search Results template	
Common tags and arguments Authentication template Two-factor authentication templates Welcome template Search Forms template Search Results template Expanded Entry template	
Common tags and arguments Authentication template Two-factor authentication templates Welcome template Search Forms template Search Results template Expanded Entry template Error template	
Common tags and arguments Authentication template Two-factor authentication templates Welcome template Search Forms template Search Results template Expanded Entry template Error template Modify template	
Common tags and arguments Authentication template Two-factor authentication templates Welcome template Search Forms template Search Results template Expanded Entry template Error template Modify template Modify Value Form template	32 33 34 36 38 43 43 47 58 59 61 63

New Password template	65
Assign Password template	66
Request Remove Entry template	67
Global changes templates	67
Target-object cache templates	69
Chapter 5: Format file	77
Location and syntax	77
Assessment order and examples	80
URI and link tags	
Display name tags	84
Target object tags	
Alternative hierarchy tags	
Approval process tags	
Chapter 6: Server-side attributes	91
Important note	
Concepts	91
DUA presentation operational attributes	93
Preprocessing functions	
User operational attributes	
Approval process operation attributes	126
New entry operation attributes	127
Other operational attributes	
Chapter 7: Printing DUA	
Running the Printing DUA	135
Input script syntax	
Supported attribute syntaxes	147
Chapter 8: Printing DUA scripts	149
phonelist.ds	149
unitlist.ds	151
executivelist.ds	153
mailinglist.ds	154
staffdetails.ds	
Chapter 9: Advanced features	159
Configuring proxy authorization for SSO	159
Configuring external SAML authentication	

Configuring related-entry workflow	163
Configuring the approval process	164
Configuring for two-factor authentication	166

Chapter 1: About this guide

This guide provides information about two ViewDS user interfaces, Access Presence and the Printing DUA. Access Presence is a web-based DUA that allows users to search and manage directory data. The Printing DUA produces reports containing directory data, which can be generated from Access Presence.

This chapter has the following sections:

- Who should read this guide
- <u>Conventions</u>
- Related documents
- How this guide is organized

Who should read this guide

Read this guide if you are responsible for developing, modifying or configuring an implementation of Access Presence or the Printing DUA.

You will need to be familiar with HTML, and knowledge of a web-based scripting language is advantageous. You should also be familiar with Access Presence from a user's perspective (the *ViewDS Directory: Installation and Operation Guide* includes an introductory tutorial).

For information about configuring ViewDS for Access Presence, refer to the ViewDS Directory: Installation and Operation Guide.

Conventions

The Access Presence tags are in Backus-Naur Form (BNF) and displayed as follows.

<VFDeleteHref [confirm] [html=1*CHAR] [id=1*CHAR]>

Where:

<>	Encloses a tag and its arguments.
[]	Encloses an optional argument.
1*CHAR	A value comprising one or more characters.

 $1 \star \text{DIGIT}$ A value comprising one or more digits.

Separates the allowable values of an argument.

For example, consider the following tag:

<ExampleTag id=1*DIGIT [confirm] [html=1*CHAR] [select=on|off]>

The name of the tag is ExampleTag and it has the following arguments:

id=1*DIGIT	Must be declared and set to a value comprising one or more digits.
[confirm]	Optional. Does not require a value and therefore acts as a flag.
[html=1*CHAR]	Optional. If declared, its value must comprise one or more characters.
[select=on off]	Optional. If declared its value must be either on or off.

Related documents

As well as this guide, the ViewDS document set includes the following:

- ViewDS Directory: Installation and Operation Guide
- ViewDS Directory Server: Technical Reference Guide
- ViewDS Access Sentinel: Installation and Reference Guide
- ViewDS Access Proxy: Installation Guide
- ViewDS Management Agent Help

How this guide is organized

Chapter 1: About this guide

Provides a brief overview of this guide.

Chapter 2: System overview

Provides an overview of the main components of Access Presence and the Printing DUA.

Chapter 3: Configuring Access Presence

Describes the Access Presence configuration files and parameters.

Chapter 4: Templates and tags

Describes the Access Presence templates and their tags.

Chapter 5: Format file

Describes the format file, its syntax and tags.

Chapter 6: Server-side attributes

Describes the server-side attributes that relate to Access Presence.

Chapter 7: Printing DUA

Describes the syntax and use of the Printing DUA scripting language.

Chapter 8: Printing DUA scripts

Describes the Printing DUA scripts that are supplied with ViewDS.

Chapter 9: Advanced configuration

Includes procedures to configure for 'single sign on', related-entry workflow and the approval process.

Chapter 2: System overview

This chapter provides an overview of the Access Presence web DUA and the Printing DUA, their major features and where they fit into the ViewDS architecture. You will need this background information before adapting either.

This chapter has the following sections:


- Overview of Access Presence
- Overview of the Printing DUA

Overview of Access Presence

This subsection introduces the main components and functionality of Access Presence.

Main components

Access Presence is the ViewDS web-based client. The following illustration shows Access Presence, the template and format files it uses to construct web pages, the configuration files it accesses, and the Directory System Agent (DSA) and ViewDS Management Agent.



Access Presence constructs web pages containing directory data obtained from the DSA. How this data is presented is defined by template files, the format file, and the DUA presentation data stored by the DSA. Additional configuration and presentation data is stored in the Access Presence configuration files and the ViewDS configuration file.

Templates

The Access Presence user interface comprises twelve web pages. Each is constructed from a template file, which is a text file containing standard HTML tags plus proprietary Access Presence tags.

When a user requests a particular page, Access Presence substitutes the proprietary template tags for HTML tags and other information. Some of the Access Presence tags are replaced by directory data, which Access Presence obtains from the DSA, while others are replaced by links to Access Presence functions or pages.

The templates and tags are described in Templates and tags.

Format file

The format file contains Access Presence tags that give a finer level of detail than is possible through the tags in the Search Results and Expanded Entry templates.

The format file and its tags are described in Format file .

Access Presence configuration files

There are three Access Presence configuration files:

- Extra template file identifies extra templates that can be used in place of the standard Expanded Entry template.
- MIME mapping file defines MIME types to associate with attribute types. It allows users to download attributes of any type to a file of the correct type.
- Post-processing command file defines the processing to perform on an attribute value, and is used to generate URIs from attribute values.

The above files are described in <u>Configuration files</u>.

ViewDS configuration file

Access Presence reads parameters in the ViewDS configuration file. These parameters are described in <u>Configuration files</u>.

Directory System Agent

The DSA provides the following to Access Presence:

- directory data which Access Presence uses to replace template tags.
- Basic Access Control Items these access controls can be assigned to users to control their access to objects and attributes in the directory. They can be defined using the Stream DUA or ViewDS Management Agent.

 DUA presentation data – which defines, for example, the appearance of entries, attributes and Search Forms. This data is stored in operation attributes, which can be managed through either the Stream DUA (see <u>Server-side attributes</u>) or the ViewDS Management Agent (see below).

ViewDS Management Agent

The ViewDS Management Agent allows you to manage the DUA presentation data stored by the DSA. This data defines, for example, the appearance of attributes, object classes and Search Forms.

For information about managing presentation data through the ViewDS Management Agent, see the topics listed under Defining DUA presentation in the application's help system.

Main functionality

The main functionality of Access Presence includes the following:

- Search forms
- Global changes
- Target objects
- Context attributes
- Alternative hierarchy
- Report printing
- Approval process

Search forms

Access Presence allows the user to select from a choice of Search Forms through which to search the directory. Each form has a definition that includes details such as which attributes are available for the user to search on, and how the results are sorted.

The ViewDS Management Agent allows you to define and manage Search Forms – see the ViewDS Management Agent help topic View or modify a Search Form.

Global changes

An Access Presence user can now make a change to an attribute's value in multiple entries – referred to as making a global change. To illustrate, if a user changes an attribute's value globally, all instances of the attribute (within the scope of the change) are then set to the new value.

Before a user can apply global changes, the ViewDS DSA must be configured to enable this functionality (see <u>Configuring for global changes</u>).

Target objects

Several Access Presence pages have links relating to the target-object cache – for example, these links include 'Set target object' and 'Show target object'.

The 'Set target object' link allows the user to designate an entry to be a target object by placing it in the target-object cache. The user can then apply actions to the target object. For example, when they:

- move an entry the target object will become its new superior
- print a report the target object will be the base object for the report
- click 'Show target object' the target object will be displayed

The entry remains in the target-object cache until the user selects 'Set target object' for another entry.

Alternatively, the user can add multiple entries to the target-object cache (for example, by selecting an 'Add to cache' link). The user can then apply actions to all entries in the cache, such as adding them to a group.

This guide describes the templates and tags that allow the user to use target objects.

Context attributes


These are attributes to which a user can assign default values – they do this by entering values and then 'setting the context' in a Search Form. These default values are then assigned to the appropriate context attributes whenever the user subsequently performs a search. That is, until the user removes the default values (by 'clearing the context').

Before the 'set context' functionality can be applied to an attribute, it must first be declared a 'context attribute'. You can do this through the ViewDS Management Agent – see the help topic *Manage context attributes*.

Alternative hierarchy

The entries in a directory are arranged in a directory hierarchy. Access Presence presents this arrangement and can also display alternative hierarchies.

As a simple illustration, consider a directory hierarchy where entries are organised according to their department. The following illustration shows the members of the Test Department at Widgets and Springs Incorporated.



When Access Presence displays the Expanded Entry page for a department member, it also lists the remaining members at the same level in the hierarchy. There is, however, no quick way of

seeing who reports to who within the department – Sarah Ng is actually the manager of the Test Department, but this is not conveyed.

The board of Widgets and Springs Inc now decide they wanted to see the managerial relationships within their organization. This can be achieved through Access Presence by incorporating template tags for an alternative hierarchy. In this case, the tags base the alternative hierarchy on the value of each entry's 'ReportsTo' attribute.

With this implementation, when Access Presence displays details of a department member, it also shows the alternative hierarchy. So, when Sarah Ng's entry is displayed, all employees who report to her – the rest of the testers – are listed as subordinates.

Report printing

ViewDS includes the Printing DUA which runs print scripts that specify the entries to be extracted from the directory and any subsequent manipulation. Users can run these print scripts from the Print Form page of Access Presence.

Approval process

This mechanism imposes an approval process on changes to the directory.

A user is designated either a 'requestor' or an 'approver'. A requestor can submit a request to modify, delete or move an entry. Later, a user with appropriate access rights, an approver, can either approve or reject the request.

To enable the approval process, see <u>Configuring the approval process</u>.

Access Presence cookies

Access Presence may make use of three different session cookies:

- vds-session-id-the session ID of the managed session (see <u>Directory-based session</u> management)
- VF_Pass the credentials of the current user
- VF_TARGET_O details of the target object

Cookie Security

Both vds-session-id and VF_Pass are HttpOnly cookies. This means that on a supported browser, they will be used only when transmitting HTTP (or HTTPS) requests.

All three session cookies used by Access Presence can be set up as Secure cookies. This means that they can only be used via HTTPS, so they are always encrypted when being transmitting from client to server. To use Secure cookies set the webcookiesecure configuration file option to on.

Session management

Two different types of session management can be employed by Access Presence:

- Cookie-based
- Directory-based

Cookie-based session management

User credentials and a session expiry are stored in the VF Pass session cookie.

To use cookie-based session management websessionenabled must be set to off and an integer value for websessionexpiry must be provided. This value, if greater than 0, represents the permitted lifetime of the VF_Pass cookie in seconds. The default value of 0 indicates that the VF_Pass cookie has an unlimited lifetime.

Directory-based session management

Sessions are maintained as objects within ViewDS and only the session IDs are stored in the vds-session-id session cookie.

To use directory-based session management websessionenabled must be set to on and the credentials of the user account used for managing session objects in the directory must be provided in websessionuser and websessionpassword.

This user account must have the necessary permissions to be able to maintain viewDSSessionObject operational attribute values in their entry. The proxyAgent attribute must also be present.

By default the websessionexpiry for sessions managed by the directory is set to 28800s (8 hours). This expiry is calculated from the time the user last authenticated to Access Presence. When the session expires the user is redirected to the authentication form.

The websessioncleanup configuration file option provides a clean-up mechanism for directory-based sessions. It is an integer with a default value of 86400s (24 hours) and represents the maximum age of a session object in the directory in seconds. When Access Presence adds or removes a session object for the current user, it checks for any other session objects older than this and removes them as part of the same modify operation.

Overview of the Printing DUA

The input to the Printing DUA is a script and its output is an ASCII file. The script specifies the entries to be extracted and any subsequent data manipulation. The Printing DUA can sort the extracted data and insert data (text, tabs, tags, line breaks, etc.) as required.

The Printing DUA scripts can be invoked from Access Presence or from some other mechanism external to the directory – such as, the command line or a batch file or scheduler.

Input script

The input script to the Printing DUA specifies:

- the data to be extracted
- the order in which the data is to be outputted
- the format of the outputted data

A major feature of the Printing PDU is flexible output - this feature enables a user to specify the form of the output information. Therefore, if it is intended that the output should be:

- read as plain text, it is generated so that it is as readable as possible.
- the input into another computer system or application (such as a word processing application), it is generated in the form required by the target system or application.

Output file

Although the functionality of the Printing DUA is powerful, there may be occasions where it cannot quite produce the precise output required. In this case, it will be necessary to output data close to the requirement and then process it further with any general purpose programming language.

When a formatted document is required, the Printing DUA's output can be fed into a target application. To accommodate this it is usually necessary for the Printing DUA to generate 'tagged data'. The target application can then be used to publish the document – for example, by setting the fonts, headers, footers, table of contents, and adding text and graphics as required.

Chapter 3: Configuration files

This chapter describes the configuration files accessed by Access Presence, and also describes how to configure for printing.

It has the following sections:

- <u>Access Presence configuration files</u>
- ViewDS configuration file
- Additional Access Presence files
- Configuring for printing
- <u>Configuring for global changes</u>

Access Presence configuration files

This section describes the following configuration files that are specific to Access Presence:

- Extra template file
- MIME mapping file
- Post-processing command file

Extra template file

The extra template file identifies 'extra templates' that can be used in place of the standard Expanded Entry template or Search Results template.

Many of the Access Presence tags generate a URI – for example, VFAuthURI and VFSearchURI. These tags have an optional id argument that identifies an extra template to be included in the URI in place of the standard Expanded Entry template. Whenever a user subsequently views the Expanded Entry page, it is generated using the extra template identified in the URI. To revert to the standard Expanded Entry template, the id argument must be set to `default`.

Each extra template can also be associated with a *template-specific format file*, which is defined in the same way as the <u>standard format file</u>. The extra template then uses its template-specific format file plus the standard format file. (The definitions in the template-specific format file, however, take precedence over those in the standard format file.)

NOTE: The page generated from an extra template can also be accessed from a standard Access Presence page using the <u>VFURI or VFHref tags</u>.

Location

The file is identified by the configuration-file parameter <u>webExtraTemplateFile</u>.

Syntax

Each line in the extra template file identifies an extra template:

identifier%content_type%disposition% extraTemplate extraFormat

Where the % character is a delimiter, and:

- identifier is an alphanumeric string without any spaces.
- content_type is optional and identifies the content type (for example, <code>%text/xml</code>) to appear in the HTTP content-type header of the page generated from the template. If no content type is declared, the default %text/html applies. If the content type is declared starting with <code>%text/</code>, then ; charset=... is appended to the content-type header and the character encoding is set to UTF-8.
- disposition is optional and identifies the HTTP content-disposition header of the page generated from the template. It can include spaces and quotation marks, but cannot include a % character as this is used as a delimiter.
- extraTemplate is the path and name of a template file relative to the webdir directory (by default, \${VFHOME}/webdir or %VFHOME%\webdir).
- extraFormat is optional and identifies the path and name of a template-specific format file relative to the webdir directory (by default, \${VFHOME}/webdir or %VFHOME%\webdir).

A path and name that contains space characters must be enclosed by double-quote or apostrophe characters. These characters can be escaped using the backslash character.

The extra template file contains a maximum of 25 identifiers. (This is because Access Presence maps each identifier to a character between 'b' and 'z', which it then includes in the URI for the subsequent Expanded Entry page.)

Examples

Consider the following entries in the extra template file:

```
treeExpanded /tmpl/altTmp/tree_expanded_entry.html
maxExpanded "/tmpl/altTmp/max detail.html"
minExpanded /tmpl/altTmp/min_detail.html
min_formatFile xmlHierarchy%text/xml/tmp/altTmp/xmler.xml
```

They declare three extra Expanded Entry templates identified by the strings treeExpanded, maxExpanded and xmlHierarchy.

Now, consider the following Access Presence tag:

```
<VFWelcomeURI [id=*CHAR]>
```

This tag can be used in a template to generate a URI to the Welcome page:

<A HREF="<VFWelcomeURI>">Welcome page

It can also be used to identify an alternative Expanded Entry template to be included in the URI:

<A HREF="<VFWelcomeURI id=treeExpanded>">My details

Access Presence will then use the template file tree_Expanded_Entry.html when the user views the Expanded Entry page.

NOTE: To revert to the standard Expanded Entry page, a template must set the id argument to `_default`.

The last example above, xmlHierarchy, is slightly different to the other two examples. It defines that the MIME type to be generated from the template is XML.

MIME mapping file

The MIME mapping file defines MIME types to associate with attribute types. It allows users to download attributes of any type to a file of the correct type.

Location

The location is set by the configuration-file parameter <u>webAttMIMEMappingFile</u>.

Syntax

The file comprises one or more lines that take the following format:

```
entry ::= attributeReference wp mimeType [ wp message ] eol [ tab
disposition eol ]
wp ::= ' ' | '\t'
eol ::= [ '\r' ] '\n'
attributeReference ::= attributeTypeName [ "." componentReference ]
```

Where:

- attributeTypeName the name of an attribute type.
- mimeType the MIME type used as the content-type HTTP header when the attribute value is downloaded to a browser.
- componentReference the component reference of a field within the attribute value. The component reference syntax is defined in the following RCF: Legg, S (2004), LDAP & X.500 Component Matching Rules, http://tools.ietf.org/html/rfc3687. A component reference allows any field within a syntax defined as an ASN.1 type to be referenced.
- disposition a string used as the content-disposition HTTP header when the attribute value is downloaded to a browser.
- message the message displayed in the browser to represent this attribute value.

The entries are evaluated in the order they occur in the file.

The attributeReference is a Boolean assertion on the attribute value. The first entry with an assertion in the attributeReference that evaluates to true provides:

- an attribute-type name, which will match any value of the identified attribute;
- an attribute-type name with a component reference of a field in the value of the attribute, which will match any value of the attribute in which the referenced field is present;
- an attribute-type name with a component reference of a bit in a BitString field in the attribute value, which will match any value of the attribute in which the referenced BitString is present and the identified bit is set.

The message field may contain some special character sequences, which Access Presence will replace with certain values. These sequences are:

- %s which will be replaced with the URI required to download the value. (Previous versions of this file used a single % character for this purpose.)
- % { . . . } where the braces contain a comma-separated list of component references. This expression will be replaced by the string value of a field in the attribute value identified by the component reference list. The component references are evaluated from left to right until a reference to a field present in the current value is found. Where the identified field is a string field, the string is converted into an appropriate code page (currently ISO-8859-1); otherwise the field is encoded into a string (of the appropriate code page) using the generic string encoding rules described in the following RCF: Legg, S (2003), *Generic String Encoding Rules for ASN.1 Types*, http://tools.ietf.org/html/rfc3641.
- %% which will be replaced with an explicit % character.

The disposition field may also contain some special character sequences that Access Presence will replace with certain values. The { . . . } and character sequences described for the message field are supported for the disposition field.

Examples

These three examples are from the MIME mapping file, att.mime, supplied with the demonstration directory, Deltawing.

Example 1

This example tells Access Presence that attributes of the type photo should be treated as the MIME type image/jpeg:

photo image/jpeg

Example 2

This example tells Access Presence to display attributes of type document as the MIME type application/pdf.

document application/pdf

Example 3

This example maps the attribute type cACertificate:

cACertificate application/pkix-cert Download certificate for %
{toBeSigned.subject.rdnSequence.-1.*.value} application; filename="%
{toBeSigned.subject.rdnSequence.-1.*.value}"

Where:

- cACertificate the attribute type in the directory.
- application/pkix-cert-the MIME type.
- Download certificate for % {toBeSigned.subject.rdnSequence.-1.*.value} the component reference displayed by the browser.
- application; filename="%{toBeSigned.subject.rdnSequence.-
 - 1.*.value}"

- the disposition which defines the file name to which the certificate will be saved when downloaded by the user.

Post-processing command file

This file defines the processing to perform on an attribute value, and is used to generate URIs from attribute values.

Location

The file's location is set by the configuration-file parameter $\underline{webPostProcessCmdFile}$.

Syntax

The file comprises one of more lines as follows:

```
attribute-name [output-string] [attribute-names]
```

Where:

- attribute-name is the name of an attribute type.
- output-string is the string to display in place of the attribute value.
- attribute-names is a list of attributes whose values are substituted for `%' or `\$' characters in output-string. A value substituted for a `%' has characters that are illegal in URIs suitably escaped, so use a `%' is the value is to appear in a URL. A value substituted for a `\$' is not altered.

For example (a single line):

telephoneNumber "\$" telephoneNumber commonName location telephoneNumber

ViewDS configuration file

This section describes the parameters in the ViewDS configuration file that relate to Access Presence. By default, the configuration file is $\{VFHOME\}/setup/config$ or $VFHOME \setup/config$.

All paths specified by the parameters are either absolute or relative to the webdir directory. The parameters are grouped as follows:

- General parameters
- Authentication parameters
- Two-factor authentication parameters
- Search Form parameters
- Search Results parameters
- Search parameters
- Display and format parameters
- Image parameters
- Template location parameters
- Other template-related parameters

General parameters

dsaAddress

The default base address and protocol for connections to the DSA.

If Access Presence is installed on a different host to the one running the DSA, the dsaAddress should be set to the TCP/IP address and port of the DSA. However, if this is not possible, the parameter webduaaddress can be set to an address and protocol for Access Presence to use.

baseEntry

The Distinguished Name (DN) of the subschema administrative point in Stream DUA notation (see *ViewDS Directory Server: Technical Reference Guide*).

For example: baseentry = { 0 "Deltawing" }

This parameter allows Access Presence to retrieve schema and DUA Presentation data. Access Presence also uses this parameter as the default base entry for searches. No default.

webdir

The directory containing the Access Presence configuration and data files.

Default: webdir = \${VFHOME}/webdir

webduaAddress

The base address and protocol for connections to the DSA by Access Presence. The parameter enables support for OSI protocol connections over RFC1006, and can be set to a lightweight stack address, IDM protocol address or OSI protocol address.

If this parameter has been set, then it defines the protocol and address that Access Presence uses to connect to the DSA. Otherwise, Access Presence connects to the DSA using the default protocol and address defined by the dsaAddress.

webDUAParamPath

The path of the directory where Access Presence stores cached DUA Presentation information. This path must be unique for each instance of Access Presence.

Default: webDUAParamPath = \${VFHOME}/webdir/conf

webMaxRequestsPerServer

The maximum number of requests that an instance of Access Presence will handle before it terminates and is restarted.

Default: webMaxRequestsPerServer = 50

webCGITimeLimit

The maximum number of seconds that an instance of Access Presence will handle one request before it terminates and is restarted.

Default: webCGITimeLimit = 120

webUseUuid

Determines how Access Presence references entries in the URLs it generates:

- on use the entryUUID attribute (see RFC 4530) to generate a URI to identify an entry. When the entryUUID attribute is unavailable, the entry's DN is used.
- off-use the DN to generate a URI to identify an entry. This is option is available for compatibility with ViewDS prior to Version 7.0.

Default: webUseUuid = on

webSchemaArea

The Distinguished Name of a schema administrative point from which Access Presence obtains schema and parameterisation information. This parameter is of use for a distributed environment in which schema and parameterisation information is unavailable in some areas of the DIT.

There is no default for this parameter.

webcookiesecure

A Boolean that defines whether the Secure property is set for the VF_Pass, VF_TARGET_ O and vds-session-id cookies.

Default: webcookiesecure = off

websessionexpiry

If websessionenabled = off, then this is an integer value that, if greater than 0, represents the permitted lifetime of the VF_Pass cookie in seconds. The default value of 0 indicates that the cookie has an unlimited lifetime.

If websessionenabled = on, then this is an integer value that represents the permitted lifetime of a log in session in seconds. The default value of 28800 indicates that the session has an 8 hour lifetime.

websessionenabled

A Boolean that controls whether directory-based session management is used. When this is set to on Access Presence will use session objects stored in the directory. The VF_Pass cookie will be deleted and a new cookie called vds-session-id will be used that contains only a randomly generated session identifier. This cookie will have the HttpOnly attribute set and will have the Secure attribute set if the webcookiesecure configuration file option is set to on.

Default:websessionenabled = off

websessionuser

A string containing the LDAP string encoded DN or the username of the account Access Presence should use for managing session objects in the directory.

This configuration file option is only required if websessionenabled = on.

websessionpassword

A string containing the password of the account identified in websessionuser.

This configuration file option is only required if websessionenabled = on.

websessioncleanup

An integer that represents the maximum age in seconds of session objects in the directory. This is used to clean-up sessions managed by the directory. When Access Presence adds or removes a session object for the current user, it checks for any other session objects older than this period and removes them.

```
Default: websessioncleanup = 86400 (24 hours)
```

Authentication parameters

webRequireLogin

A Boolean that defines whether Access Presence performs login authentication each time the directory is accessed.

Default: webRequireLogin = on

webBindUser

Defines the user name and password that Access Presence uses to bind to the directory. It is used if webRequireLogin is off or webProxyUser is on.

Example:webBindUser = vfsuper passwd

webProxyUser

A Boolean that enables proxy authentication.

Default: webProxyUser = off

webProxyAuthAttribute

Access Presence uses this parameter to map an identity determined by an external agent (such as a web server or a SAML IdP) to an entry in the ViewDS directory. It is used when webProxyUser is on or when a websamlentity is specified.

Default: webProxyAuthAttribute = userName

websamlentity

Defines the URI used to identify the Access Presence service provider entity for external SAML2 authentication (app_id_uri). If this configuration option is specified, then SAML2 authentication, using the SAML2 Web SSO profile, is enabled and the additional configuration options websamlidpurl and websamltrustanchor must also be provided.

websamlendpoint

Identifies an optional call-back URL for Access Presence, to be included in SAML2 authentication requests made by Access Presence. If this configuration option is not provided, then call-back information will not be included in the SAML2 request and it is assumed that the SAML2 identity provider will be configured with an appropriate default value. The SAML2 endpoint should be the URL of Access Presence without any query string or subsequent path components.

websamlidpurl

Defines the URL of the external SAML2 identity provider authentication endpoint.

websamltrustanchor

Specifies the file name of the certificate that Access Presence should use to verify the signature on the SAML assertions provided by the SAML2 identity provider. The signature may be verified directly or through a certificate path provided the intermediate certificates are included in the X509Data element of the SAML2 assertion with the signing certificate.

webAnonymous

A Boolean that governs whether Access Presence requires the user to provide authentication information to log in to the directory. When this parameter is set to on, Access Presence will not initially prompt for a user login. If it does prompt for authentication information (see the <u>VFAuthURI tag</u>), it will permit the Access button to be selected without any information being provided in the other input fields.

This parameter differs from webRequireLogin by explicitly supporting anonymous logins, whether the authentication form is used or not. It is recommended that webRequireLogin is set to on when this parameter is used.

Default: webAnonymous = off

webRemoteUser

Sets the name of the environment variable used by a web server to pass an authenticated identity to a CGI during <u>proxy authorization</u>.

```
Default: webRemoteUser = REMOTE USER
```

webUsePassword Policy

A Boolean that defines whether Access Presence should use password policy controls in requests.

Default: webUsePasswordpolicy = off

Two-factor authentication parameters

webSessionAuthenticator

Specifies the attribute in a user's entry that stores their authenticator secret. The authenticator secret allows a user to confirm a time-based one-time password (TOTP) from a third-party authenticator, and therefore enable two-factor authentication on their Access Presence account.

This attribute should be:

- Available to the account used for managing session-state information.
- Single valued (multiple values are not supported).
- Protected by access controls so that its value is only visible to the user and administrators responsible for account management. It may be desirable to provide access controls to allow applications to determine whether the attribute is present (without revealing the value) and therefore whether a user has enabled two-factor authentication on their account.

Default: Not applicable

Search Form parameters

webSelectableField

Determines whether the Search Form page present search fields that are:

- restricted to one specific attribute (off)
- allow an attribute to be selected from a drop-down list (on)

Additionally, if a set of possible values is declared for an attribute in its schema, and this parameter is off, the Search Form presents the values in a drop-down list.

Default: webSelectableField = on

webNumDefaultFields

Defines the number of active search fields which Access Presence will show on the Search Form page. An active field is a field which has an attribute assigned to it. This parameter is ignored if webSelectableField is off. Its maximum value is 10.

Default: webNumDefaultFields = 5

webNumDisplayFields

Defines the total number of search fields to display. If webSelectableField is on, Access Presence will show a number of inactive fields equal to webNumDisplayFields minus webNumDefaultFields. Each inactive field is labelled `----' in the search form. These are the extra fields which the user can use if webNumDefaultFields number of search fields are not enough for specifying their query. Its maximum value is 10.

Default: webNumDisplayFields = 8

webUserOptions

Determines whether Access Presence appends the search options to the Search Form.

Default: webUserOptions = on

webForceLocalSchema

Determines whether Access Presence uses the schema in the default base entry if there is no schema under the base entry associated the current Search Form.

Default: webForceLocalSchema = off

webRelatedSearchTemplate

Specifies a template to be used instead of the Search Form template during the <u>related</u>-<u>entries workflow</u>. When this parameter is unspecified, the template specified by webSearchTemplate is used.

Search Results parameters

webRelatedSearchResultTemplate

Specifies a template used instead of the Search Results template during the <u>related-entries</u> <u>workflow</u>. When this parameter is unspecified, the template specified by webSearchResultTemplate is used.

webSortStrategy

Specifies the algorithm used to sort the results displayed on the <u>Search Results page</u>. The arguments are:

- sortKeys sort the fields by the sort keys in the Search Form. The sort key is defined through the operational attribute <u>searchOptions</u> – for example, through the ViewDS Management Agent (see the help topic *View or modify a Search Form*).
- searchFields sort the fields using the first completed field on the Search Form as the initial key, then use the sort keys in the Search Form.
- firstValueExactMatch start the results with any entry where the first value of the search attribute exactly matches the value entered in the Search Form. Then, sort using the searchFields algorithm described above.
- anyValueExactMatch start the results with any entry where any value of the search attribute exactly matches the value entered in the Search Form. Then, sort using the searchFields algorithm described above.

Default:webSortStrategy = firstValueExactMatch

pagedresultcachesize

Specifies how many sets of paged search results can be stored in cache.

When a user requests a search with paged results, the first page of results is returned, and the set of remaining results is stored in cache.

The least recently viewed set of results is discarded if:

- the number of sets in cache equals the value of this parameter; and
- a user submits a request for paged search results.

When a single user has multiple sets of results in the cache, their least recently viewed set is discarded if:

- the number of sets they have in cache is half or more than the value of this parameter; and
- another user submits a request for paged search results.

This prevents a user from monopolizing the cache.

Default: 6

Search parameters

These parameters define the search options when webUserOptions is off, and the default values when webUserOptions is on.

webDefSizeLimit

The default size limits. The size limit setting here is only used if there is no user or systemwide setting stored in the directory.

```
Default: webDefSizeLimit = 100
```

webDefTimeLimit

Specifies the default time limits. The time limit setting here is only used if there is no user or system-wide setting stored in the directory.

Default: webDefTimeLimit = 10

webShowDetail

Determines whether Access Presence allows the 'expand' operation for the entries returned from a successful search. It overrides webDetailOnSingleMatch.

```
Default: webShowDetail = on
```

```
webShow = {Sub | SubAndLeaves | Icon | IconAndLabel | All}
```

This parameter defines what is displayed by the Expanded Entry page.

The arguments are:

- Sub display all non-leaf entries one level down from the expanded entry.
- SubAndLeaves display all entries one level down from the expanded entry.
- Icon use descriptive icons only as labels to the entry's attributes.

- IconAndLabel use both icon and text description as labels to the entry's attributes.
- All all of the above options apply.

All the above options except All may be used together on the same line. By default, none of the options are set.

Example: webShow = All

webDetailOnSingleMatch

Determines whether Access Presence automatically expands an entry if it is the only match returned by a search.

Default:webDetailOnSingleMatch = on

webDefExactMatch

Determines whether Access Presence does normal approximate matches the first time (off); or whether it does an exact match search, and if there are no matches, follows this with an approximate match search. This two-stage search gives a faster response with large databases.

Default:webDefExactMatch = off

Display and format parameters

webAttMIMEMappingFile

The path (relative to the webdir directory) to the MIME mapping file.

webPostProcessCmdFile

The path (relative to the webdir directory) to the Post-processing command file.

webTargetObject = on | off

Controls whether the target-object links (see <u>Target-object cache templates</u>) are displayed to all users (on) or just those with either of the following (off):

- the super-user privilege of ViewDS Access Control (see the ViewDS Management Agent help topic Set the ViewDS Access Control for an entry).
- the Printing capability of the default entitlements (see the ViewDS Management Agent help topic View or modify default entitlements for DUA users).

Image parameters

All images should be .gif files for general compatibility.

webBackGroundPic

Path and file name for the background image displayed by the Access Presence pages.

webHeaderPic

Path and file name for the header image displayed on all Access Presence pages.

webHeaderPicDesc

Text description of the header image (for text-only browsers).

webFooterPic

Path and file name for the footer image displayed on all Access Presence pages.

webFooterPicDesc

Text description of the footer image (for text-only browsers).

Template location parameters

The default Access Presence pages are built-in. However, their equivalent HTML source is provided under the 'suggested' file names below.

webAuthTemplate

Authentication template path and file name.

Suggested:webAuthTemplate = tmpl/auth.html

WebEnableAuthenicatorTemplate

Enable Two-Factor Authentication template path and file name.

Suggested: Not applicable

WebDisableAuthenicatorTemplate

Disable Two-Factor Authentication template path and file name.

Suggested: Not applicable

WebAuthenicatorTemplate

Two-Factor Authentication template path and file name.

Suggested: Not applicable

webWelcomeTemplate

Welcome template path and file name.

Suggested:webWelcomeTemplate = tmpl/wel.html

webSearchTemplate

Search Forms template path and file name.

Suggested:webSearchTemplate = tmpl/s.html

WebSearchResultTemplate

Search Results template path and file name.

Suggested:webSearchResultTemplate = tmpl/sr.html

WebExpandResultTemplate

Expanded Entry template path and file name.

Suggested:webExpandResultTemplate = tmpl/er.html

webErrorTemplate

Error template path and file name.

Suggested:webErrorTemplate = tmpl/error.html

webModifyTemplate Modify template path and file name. Suggested:webModifyTemplate = tmpl/mod.html webModifyValueTemplate Modify Value template path and file name. **Suggested**: webModifyValueTemplate = tmpl/modval.html webAddTemplate Add template path and file name. **Suggested**:webAddTemplate = tmpl/add.html webPrintFormTemplate Print Form template path and file name. Suggested:webPrintFormTemplate = tmpl/pf.html webPrintTemplate Print template path and file name. Suggested:webPrintTemplate = tmpl/pr.html webNewPasswordTemplate New Password template path and file name. **Suggested**:webNewPasswordTemplate = tmpl/npw.html webAssignPasswordTemplate Assign Password template path and file name. Suggested:webAssignPasswordTemplate = tmpl/apw.html webGlobalChangeRequestTemplate Global Change Request template path and file name. **Suggested**:webGlobalChangeRequestTemplate = tmpl/gcrequest.html webGlobalChangeConfirmTemplate Global Change Confirm path and file name. **Suggested**:webGlobalChangeConfirmTemplate = tmpl/gcconfirm.html webGlobalChangeResultTemplate Global Change Results path and file name. **Suggested**:webGlobalChangeResultTemplate = tmpl/gcresult.html WebShowTargetObjectsTemplate Show Target Objects template path and file name. **Suggested**:webShowTargetObjectsTemplate = tmpl/showtarget.html

webSelectTargetObjectTemplate

Select Target Object template path and file name.

Suggested:webSelectTargetObjectTemplate = tmpl/selecttarget.html

webSelectImportsTemplate

Select Entries to Import template path and file name.

Suggested:webSelectImportsTemplate = tmpl/selectimports.html

webSelectRemovalsTemplate

Select Entries to Remove template path and file name.

Suggested:webSelectRemovalsTemplate = tmpl/selectremovals.html

WebAltAddSelectionTemplate

Select Entries to Add to Alternative Hierarchy template path and file name.

Suggested:WebAltAddSelectionTemplate = tmpl/altaddselection.html

webAltMoveSelectionTemplate

Select Entries to Move in Alternative Hierarchy template path and file name.

Suggested:webAltMoveSelectionTemplate =
tmpl/altmoveselection.html

$web {\tt Request} {\tt Remove} {\tt entry} {\tt Template}$

Request Remove Entry template path and file name.

```
Suggested:webRequestRemoveEntryTemplate =
tmpl/requestremoveentry.html
```

Other template-related parameters

defaultCharSet = character_set

Deprecated.

webTemplAttribute = attribute_name

This parameter allows an alternative Expanded Entry template to be invoked for a specific directory entry. The entry must include an attribute whose name matches the value of the webTemplAttribute parameter. The value of this attribute should be the name of the alternative Expanded Entry template to be invoked.

For example, consider a directory entry that includes the attribute specialTemplate
whose value is the name of an Expanded Entry template for people in the Finance
Department:

specialTemplate = tmpl/financeExpEntry

To invoke the template, the webTemplAttribute parameter must be set to the name of the above attribute:

webTemplAttribute = specialTemplate

Different entries can include the specialTemplate attribute with values that invoke different templates.

webExtraTemplateFile

The path (relative to the webdir directory) to the Extra template file. For Deltawing, the default is: tmpl/extra.lst

webFormatFile

The path (relative to the webdir directory) to the format file.

A supplied example is: tmpl/format.lst

webstartpage

Declares which page is displayed after a user has been authenticated.

By default, a user authenticates by entering their user name and password on the Authentication page, and Access Presence then displays the Welcome page.

This default behaviour can be changed by setting the webstartpage parameter to one of the following arguments:

- search the Search Form is displayed after authentication
- baseentry-the Expanded Entry page for the base entry is displayed after authentication
- userentry-the Expanded Entry page for the authenticated user is displayed after authentication (if there is no entry for the user, the base entry is displayed)

If this parameter is not declared (or set to welcome) the default behaviour applies.

Additional Access Presence files

The demonstration directory, Deltawing, uses additional files in the following locations:

- webdir/help-this directory contains help files for Access Presence.
- webdir/icons/newicons contains icons that are included in Expanded Entry pages.
- webdir/tmpl-contains the sample templates described in Templates and tags.

Configuring for printing

A user can invoke a Printing DUA input script from a menu on the <u>Print Form page</u> and to select a base object for the script.

The content of the menu is configured in the following file:

\${VFHOME}/setup/printconfig

Each line of this file contains the following fields in this order, separated by the $\$ character:

- label a descriptive label for the report
- script name the name of the PDUA script used to extract the data form the report (in \${VFHOME}/print).

- post processing script the name of an optional Shell script to process the extracted data (in \${VFHOME}/print). This field may be empty.
- content type the Content-Type value to use when delivering the report to the browser. This field may be empty.
- content disposition the Content-Disposition value to use when delivering the report to the browser. This field may be empty.

The supplied printconfig file lists the supplied scripts (see <u>Printing DUA scripts</u>).

Configuring for global changes

Before an Access Presence user can apply global changes to the values of attributes, you must configure the ViewDS DSA to enable this functionality. You can configure the DSA using either the Stream DUA or ViewDS Management Agent.

For the ViewDS Management Agent, see the help topic Configure for global changes.

For the Stream DUA:

- 1. Enable an attribute for global changes by setting its globallyChangeable flag in the operational attribute <u>attributePresentation</u>.
- 2. Allow users to apply global changes by setting the globalChanges flag in either <u>defaultEntitlement</u> or <u>userEntitlement</u>.

Chapter 4: Templates and tags

This chapter describes the Access Presence templates and tags. It includes example code from the demonstration directory supplied with ViewDS, Deltawing. For information about using Deltawing, see the *ViewDS Directory: Installation and Operation Guide*.

This chapter has the following sections:

- Common tags and arguments
- <u>Authentication template</u>
- <u>Two-factor authentication templates</u>
- Welcome template
- Search Forms template
- Search Results template
- Expanded Entry template
- Error template
- Modify template
- Modify Value Form template
- Print Form template
- Print template
- New Password template
- <u>Assign Password template</u>
- Request Remove Entry template
- Global changes templates
- Target-object cache templates

The file names and locations of the Access Presence templates are set in the ViewDS configuration file (see <u>Template location parameters</u>).

Common tags and arguments

Common template tags

These tags can be used in any Access Presence template, except the Authentication template.

<VFUserID>

This tag is replaced by the display name of the user currently logged in.

<VFPasswordPolicyExpiry [before=1*CHAR] [after=1*CHAR]>

This tag is replaced by the number of seconds until the current user's password is due to expire and the account is locked. It generates values only when the password policy indicates that a password is due to expire. The tag takes two optional arguments before and after which can be used to provide HTML that will be put before and after the tag value.

<VFPasswordPolicyGraceLogins [before=1*CHAR] [after=1*CHAR] >

This tag is replaced by the number of grace logins permitted for the current user before their account is locked. Grace logins are provided after a password expires to permit the user to change their password. The tag generates values only when a password has expired and the grace logins apply. It takes two optional arguments before and after which can be used to provide HTML that will be put before and after the tag value.

<vfuserURI [id=*CHAR]>

This tag is replaced by the URI for the Expanded Entry page displaying the entry for the currently authorized user.

The *id argument* is common to many tags.

<VFDN>

This tag is replaced by the LDAP DN of the entry displayed by the Expanded Entry page.

<VFSetSearchForm name=1*CHAR>

This tag allows the Search Form to be specified in a template. Within the scope of the VFSetSearchForm tag, the Search Form selected on the Welcome page is overridden by the Search Form specified in the tag's name argument.

The block must be terminated with an end tag:

```
<VFSetSearchForm name="Name Search">
<form action="<VFSearchURI>">
<!-- HTML for simple search form -->
</form>
</VFSetSearchForm>
```

<VFBaseDNURI [id=*CHAR]>

This tag is replaced by the URI required to access the Expanded Entry page for the base object.

Common arguments

The following arguments are common to many template tags.

id

The id argument identifies an alternative Expanded Entry template to be included in the URI generated by the tag it appears in. The id for the alternative template must be declared in the extra template file (see Extra template file).

To revert to having the standard Expanded Entry template in the URI, set the id to '_default'.

html

The html argument should be enclosed in backquotes and should include all the text to appear between the opening <A HREF and the closing .

To illustrate, the following example would display the text 'Set Password' linked to the Assign Password page:

<VFAssPassFormHref html=">Set Password">

The default value of the html argument is >.

confirm

The confirm argument invokes a confirmation dialog when the link generated by its tag is selected by a user.

format

This argument identifies a set of format directives in the <u>format file</u>. The directives are applied to the information generated by the tag that includes the format argument.

scope

This argument changes the scope of a tag. It can be set to:

- base the scope is the base entry and its subordinates.
- user the scope is the entry for the user viewing the page and its subordinates.

Alternatively, it can be set to a specific entry identified by either:

- the value of the entry's entryUUID attribute; or
- the LDAP string representation of the entry's Distinguished Name.

Authentication template

This template generates a web page that allows a user to enter either their Distinguished Name or user name plus their password.

The template includes a form containing four Access Presence tags, which are described below.

```
<form method=post action="<VFAuthURI>">
Username: <input name="<VFAuthUserNameID>"> <br>
Password: <input type=password NAME="<VFAuthUserPassID>"> <br>
```

```
<VFAuthReferer>
<input type=submit value="Access">
</form>
```

<VFAuthURI [id=*CHAR]>

This tag is replaced by a Uniform Resource Identifier (URI) for the Authentication page. The \underline{id} argument is common to many tags.

<VFAuthUserNameID>

This tag gives the value for the HTML NAME element in the user-name input tag.

<VFAuthUserPassID>

This tag gives the value for the HTML NAME element in the password input tag.

<VFAuthReferer>

This tag ensures that Access Presence returns to the page the user was attempting to view before authentication. The tag is replaced by an HTML input element:

<input type='hidden' name='referrer' value=URL>

The value is equal to the URL for the page the user was attempting to view.

Two-factor authentication templates

This advanced feature is not available to users in the default implementation of Access Presence. For further information see <u>Configuring for two-factor authentication</u>.

There are three templates for two-factor authentication:

- Enable Two-Factor Authentication template
- Disable Two-Factor Authenticator template
- Two-Factor Authentication template

Enable Two-Factor Authentication template

This template allows the user to enable two-factor authentication for their Access Presence account. It presents a 'secret code' that the user provides to a third-party authenticator app to generate a time-based one-time password (TOTP). The user then submits the TOTP through this template to enable two-factor authentication.

<VFEnableAuthenticatorFormHref [id=*CHAR] [html=1*CHAR]>

This tag is replaced by a hypertext link to the Enable Authenticator page. Access to the page is not part of the default Access Presence configuration.

The html and id arguments are common to many tags (see <u>Common tags and</u> arguments).

<VFAuthenticatorEnableForm></VFAuthenticatorEnableForm>

This template tag is replaced by an HTML form element. Any additional parameters

declared for the tag are added to the form as HTML attributes (for example, class).

The tag should contain the two template tags shown below.

```
<VFAuthenticatorEnableForm>
<VFAuthenticatorSecretInput>
<VFAuthenticatorCodeInput>
</VFAuthenticatorEnableForm>
```

<VFAuthenticatorSecretInput [otpuri=1|0]>

This tag is replaced by a read-only HTML input element. It displays a randomly generated 'secret code' that allows the user to set up with a third-party authenticator service and obtain an TOTP.

The tag has an optional parameter, otpuri, with an integer value:

- '0' (or omitted) the 'secret code' is displayed as text.
- non-zero integer a link is displayed using the OTPauth URI scheme. This is recognized by some authenticator services, including Google Authenicator which presents an OTPauth URI to the user as a QR code.

Any additional parameters declared for the tag are added to the HTML input element as HTML attributes (for example, class).

<VFAuthenticatorCodeInput>

This tag is replaced by an HMTL text-input element, which allows the user to enter their TOTP into the template's form. On submission, ViewDS uses the TOTP to verify that the authenticator app has been set up correctly before activating two-factor authentication for the user.

Disable Two-Factor Authentication template

This template allows the user to disable two-factor authentication on their Access Presence account.

<VFDisableAuthenticatorFormHref [id=*CHAR] [html=1*CHAR]>

This tag is replaced by a hypertext link to the Disable Authenticator page. Access to the page is not part of the default Access Presence configuration.

The html and id arguments are common to many tags (see <u>Common tags and</u> <u>arguments</u>). Any additional HTML attributes declared for this tag are added to the HTML form tag that replaces it.

<VFAuthenticatorDisableForm></VFAuthenticatorDisableForm>

This template tag is replaced by an HTML form element. Any additional parameters declared for the tag are added to the form as attributes.

When a user submits the form, two-factor authentication is disabled for their account.

Two-Factor Authentication template

This template presents a form that allows the user to enter a TOTP generated by a third-party authenticator app (for example, Google Authenticate). The form should include the following tags.

<VFAuthenticatorURI [id=*CHAR]>

This tag produces the URI of the authenticator page.

It should be used to generate the ACTION parameter value for the template's form and its method should be set to post.

<form method="post" action="<VFAuthenticatorURI>">

The id argument is common to many tags (see Common tags and arguments).

This tag can also be used in the format file.

<VFAuthenticatorID>

This tag is the value of the name field in the HTML input tag for the user's TOTP.

<input name="<VFAuthenticatorID>" type="password" size="10">

The type field should be set to password so that the user's authentication code is not displayed on the screen.

This tag can also be used in the format file.

Welcome template

This template generates the Welcome page. By default, this is the first page displayed after a user has been authenticated.

NOTE: The configuration-file parameter <u>webstartpage</u> can be used to declare another page as the first to be displayed after a user has been authenticated.

The Welcome page displays a list of Search Forms from which the user can select. The Search Forms are declared through either:

- ViewDS Management Agent see the help topic View or modify a Search Form
- Stream DUA see the operational attribute $\underline{\texttt{searchOptions}}$

The Access Presence tags in the template are included in the following code, and each is described below.

```
<VFBanner> <br>
Version: <VFVersion>
<form method="post" action="<VFSearchFormURI>">
<VFSearchFormList>
<input type="submit" value="Access">
</form>
```

<VFBanner>

This tag is replaced by the contents of the 'Startup Message' box in the Banners tab of the ViewDS Management Agent (see the help topic *View or modify DUA banners*). This value is stored in the startup-message argument of the operational attribute duaBanners.

If no startup message is defined, the following default is displayed: *Welcome to ViewDS Web edition*.

NOTE : This tag can also be used in three other templates – Search Form, Search Results and Expanded Entry. In each, the tag is replaced by a different message.

<VFVersion>

This tag is replaced by the version of Access Presence that is running.

<VFSearchFormURI [restricted= {user | base | *CHAR}] [id=*CHAR]>

This tag is replaced by the URI for the Search Form selected by the user. It can be used in any Access Presence template.

restricted

The restricted argument can be used to set the base entry for the Search Form:

- user the base entry for the search is the entry for the user who is viewing the Search Form.
- base the base entry for the search is the base entry of the DIT.
- *CHAR the base entry is a specific entry identified by either the value of the entry's entryUUID attribute; or the LDAP string representation of the entry's Distinguished Name.
- no value if restricted is declared without a value, the base entry for the search will be the current entry.

When restricted is not declared, the base object is the default base object for the Search Form. This is the base object defined in the Search Form definition if present; otherwise, it is the base object of the Access Presence set by the configuration-file parameter <u>baseentry</u>).

id

The id argument is common to many tags (see Common tags and arguments).

<VFSearchFormList [showdn] [useScript=1*CHAR]>

This tag is replaced by a drop-down list containing names of available Search Forms.

The available Search Forms are declared through either the ViewDS Management Agent (see help topic *View or modify a Search Form*) or the Stream DUA (see searchOptions).

showdn

If showdn is specified, the base entry is displayed in LDAP DN string representation before the name of each Search Form in the list.

useScript

This argument invokes a call to a script function when the user selects a Search Form. The script function is identified by the argument's value.

The argument should be within a <script> tag with the language set to text/javascript (or a scripting type that supports a compatible syntax). Access Presence generates parameter values that are escaped for Javascript string content.

The call has the format: func (index, name, baseEntry, url)

Where:

- func the value of the useScript argument.
- index an integer that identifies a Search Form by its position in the sequence of Search Forms defined.
- name a string which is the name of a Search Form.
- baseEntry-an LDAP string representation of the DN of the base entry in the Search Form.
- url the URL required to access the Search Form.

<VFWelcomeURI [id=*CHAR]>

This tag generates the URI for the Welcome page, and can be used as the value of a HREF attribute in an HTML anchor tag.

The id argument is common to many tags (see Common tags and arguments).

Search Forms template

This template generates a page that allows users to search the directory using the Search Form they selected on the Welcome page.

The query input fields must be written using the HTML <FORM> and <INPUT> tags. Both POST and GET submit methods are supported, although the POST method is preferred.

Managing and defining Search Forms

The DSA stores definitions of each Search Form displayed by the Search Forms page. The definitions also describe how the results of a search are sorted and displayed by the Search Results page.

The Search Forms definitions are declared through either:

- ViewDS Management Agent see the help topic View or modify a Search Form
- Stream DUA see the operational attribute <u>searchOptions</u>

Drop-down lists

The Search Form page can be configured to present the available search attributes in dropdown boxes. It can also be configured to present an attribute's permitted values in a drop-down list. To present search attributes in a drop-down list:

• switch on the configuration-file parameter webSelectableField

To present an attribute's permitted values in a drop-down box:

- switch off the configuration-file parameter webSelectableField
- ensure that the permitted values are defined as the constrained or enumerated attribute syntax or as a result of CompareWords pre-processing function
- ensure that the attribute is not overloaded that is, in the ViewDS Management Agent, all
 values in the 'column' box of the Row Attributes window are unique (see the help topic View or
 modify a Search Form).

Attribute ID

When Access Presence starts up, it obtains DUA presentation information from the base entry in the directory. It looks at the first type of SearchForm in the searchOptions operational attribute and assigns each attribute listed in the row1-atts, row2-atts, and row3-atts attribute lists an ascending number starting from 0. These numbers – each referred to as an *attribute ID* – are used by Access Presence to name each field.

The attributes in each row of a Search Form can be managed through the Stream DUA or ViewDS Management Agent (see the help task *View or modify a Search Form*).

Attribute Name	ID
Surname	0
Given	1

To illustrate how attribute IDs are used, consider the following attributes:

A following sample query input uses the attribute IDs and FORM tag with the POST method:

```
<form method="post" action="<VFSearchURI>">
Surname: <input name="0"><br>
Given: <input name ="1"><br>
Press <input type="submit" name="<VFDoSearchID>" value="here">
to submit the query.
</form>
```

Alternatively, a template that supports only one Search Form can identify attributes using their names:

```
<form method="post" action="<VFSearchURI>">
Surname: <input name="commonName"><br>
Given: <input name="organizationalUnitName"><br>
Press <input type="submit" name="<VFDoSearchID>" value="here">
to submit the query.
</form>
```

Template tags

The Access Presence tags in the template are included in the following example code:

```
<form method="post" action="<VFSearchURI>">
 <VFSearchFields>
 <input type="image" src="../icons/b_show.gif" name="<VFDoSearchID>"
 VALUE="[ Search ]" border=0>
 <hr>>
 <a href=<VFSearchFormURI><IMG SRC="../icons/b clear.gif" alt=" [ Clear</pre>
 ]" border=0></A>
 <br>
 < input type=image src="../icons/b scontx.gif" name="<VFSetContextID>"
 VALUE="[ Set Search Context ]" border=0>
 <br>
 <input type=image src="../icons/b ccontx.gif" name="<VFClearContextID>"
 VALUE="[ Clear Search Context ] " border=0>
 <br><hr>
 <VFSearchOptions>
</form>
```

The above tags, plus others that can appear in this template, are described below.

<VFSearchURI [restricted= {user | base | *CHAR}] [id=*CHAR]>

This tag must be the value of the HTML ACTION tag in a form, and is replaced by the URI for the Search Form page. Alternatively, when it is returned in a form, the tag tells Access Presence to perform a search and output the results.

The restricted argument (see <u>Welcome template</u>) and id argument are common to many tags (see <u>Common tags and arguments</u>).

<VFSearchFieldVal [id=1*DIGIT] [spacing=1*DIGIT]>

This tag is replaced by the display name of the next attribute in the list of attributes in the Search Form. (To view or modify a display name, see the ViewDS Management Agent's help topic *View or modify an attribute's DUA presentation*.) The *id* argument allows an attribute to be identified by either its name or <u>attribute ID</u>.

spacing

Specifies a field width for the display name. If spacing is less than the length of the display name, but not zero, Access Presence truncates the display name to fit the specified width. By default, the display name is right justified – for left justified specify a negative value for spacing.

<VFSearchFields [selectable = { on | off }] [columns = 1*DIGIT]>

This tag is replaced by the default search fields defined in the selected Search Form.

selectable

If selectable is on, the field names for the search attributes are displayed in <u>drop-down list</u> <u>boxes</u> and can be selected by the user. This argument overrides the default behaviour set by the configuration-file parameter <u>webSelectableField</u>.

columns

This argument specifies the number of columns in which the search fields are displayed. If the argument is unspecified, the default of two columns applies.

<VFSearchOptions>

This tag is replaced by input boxes, drop-down lists and a check-box to allow the user to select the following search options (see Search Form parameters):

- maximum number of entries to return
- maximum time per query
- whether to show subordinates and leaves
- whether to show icons and labels
- whether to show full details if there is a single match

<VFDoSearchID>

This tag tells Access Presence to output the name for the submit field that will initiate the search. It should be used to generate the NAME parameter value of an INPUT field with TYPE="submit".

<VFBanner>

This tag is replaced by the contents of the 'Start Banner 1' box in the Banners tab of the ViewDS Management Agent (see the help topic *View or modify DUA banners*). This value is stored in the start-banner1 argument of the operational attribute <u>duaBanners</u>.

NOTE: This tag can also be used in three other templates – Welcome, Search Results and Expanded Entry. In each, the tag is replaced by a different message.

<VFSearchFormName>

This is replaced by the name of the currently selected Search Form.

<VFSearchFormURI>

This tag is replaced by the URI for the Search Form. It can be used in any Access Presence template to provide navigation to the Search Form.

<VFLDAPQueryURI [restricted= {user | base | *CHAR}]>

This tag is replaced by a URI that allows an LDAP filter string to be submitted. The tag should be the value for the ACTION attribute in an HTML FORM; the METHOD attribute of the FORM must be set to POST.

The VFLDAPQueryURI tag should be used in conjunction with VFLDAPQueryID.

The restricted argument is common to many tags (see <u>Welcome template</u>).

<VFLDAPQueryID>

This tag identifies an LDAP filter string. It should be the value of the NAME attribute in an HTML INPUT tag. The INPUT tag should be text field.

The VFLDAPQueryID tag should be used in conjunction with VFLDAPQueryURI.

Search-context tags

These tags relate to <u>context attributes</u>. To support the context attributes, the Search Form needs to display the existing values stored by the user. (This is done automatically by the default Search Form generated by the <VFSearchFields> tag.) The Search Form template uses the following tags that relate to context attributes.

<VFSetContextID>

This is replaced with the name for the submit field that will initiate the set-context operation. It generates the NAME parameter value of an INPUT field with TYPE="submit".

<VFClearContextID>

This is replaced by the name for the submit field that will initiate the clear-context operation. It generates the NAME parameter value of an INPUT field with TYPE="submit".

```
<VFSearchField name=1*CHAR [ id=1*CHAR ] [ html=`1*CHAR` ]>
```

This tag is replaced by the display name for the search field.

name

If the name argument is an attribute type or numeric identifier, the next attribute from the Search Form is displayed.

Alternatively, if the name argument is an arbitrary string (neither an attribute-type name nor a numeric identifier), this element generates a list box containing the attributes permitted on the Search Form. In this case, the id argument can be used to identify the attribute to be selected by default in the list box. Otherwise, no attribute is selected by default unless the search field is displaying an attribute from the user's search context.

html

The html argument allows extra parameters to be declared for the SELECT tag that generates the list box.

<VFQueryFieldVal name=1*CHAR [id=1*CHAR] >

This tag is replaced by the stored search-context value for a search field. (It can also appear, with a different syntax, in the <u>Search Results</u> template.)

name

The name argument identifies an attribute type in the search context to be associated with the search field. It is matched with the attribute type of a VFSearchField tag.

id

The id argument should match the id argument of the corresponding VFSearchField tag.

Search Results template

The Search Result template generates a page that presents the results of a search to the user. The results are presented in a table, each row containing a directory entry.

The DSA stores Search Form definitions, which also define the sort key for the results on the Search Results page. The sort key is defined through either:

- ViewDS Management Agent in the Results Sorting area of the Edit Search Form window (see the help topic *View or modify a Search Form*)
- Stream DUA see the operational attribute $\underline{\texttt{searchOptions}}$

The sort algorithm used is set through the configuration-file parameter <u>websortstrategy</u>.

<VFQueryFieldVal id=1*DIGIT [spacing=1*DIGIT]>

This tag is replaced by the value entered by the user in the Search Form for the search field identified by the id argument. The id argument identifies an attribute by either its name or <u>attribute ID</u>.

The spacing argument specifies a field width for the search-field value. If spacing is less than the length of the search-field value, but not zero, Access Presence truncates the search-field value to fit the specified width. By default, the value is right justified – for left justified specify a negative value for spacing.

NOTE: This tag can only be used in the Search Results template.

<VFSearchNumResult>

This tag is replaced by the number of matching entries returned by the most recent search.

<VFSearchResHeader [format=1*CHAR]>

This tag is replaced by the display names of all requested search fields in the following format: Field1: Field2: Field3:....etc

An alternative format can be imposed by setting the format element to an identifier declared in the <u>format file</u>). To view or modify a display name, see the ViewDS Management Agent's help topic *View or modify an attribute's DUA presentation*.

NOTE: The order in which the fields are displayed is the same as the order of the input fields specified in the Search Form.

```
<VFSearchResult [ useScript=1*CHAR ] [ format=1*CHAR ] [ alwaysFormat=on|off ]>
```

This tag is replaced by all matched results in, by default, a tabular format.

If the configuration-file parameter <u>webShowDetail</u> is set to on:

• for each matched result, the full DN is returned as an HTML reference attached to the result's first attribute.

- each RDN in the DN is formatted as an 'attribute=value' pair, and each RDN is separated by the & symbol.
- RDNs are in ascending (LDAP) order.
- the value in the RDN is escaped so that all '\";,%?+&/:#<>' characters and non-printable characters in the string are mapped to their hex equivalent in the ASCII character set.
- in some cases, where the attribute contains multiple values, each value is escaped as required and separated by the ^ symbol which is encoded as %2B.

For example, the name { 0 "Deltawing"/ OU "Some unit" OU "Asia" } is
encoded as:

<http://host:port/e.x500/&OU=Some%20unit%2BOU=Asia,&O=Deltawing>

useScript

This argument invokes a call to a script function that displays the search results. The script function is identified by the argument's value, and is invoked for each value of each row1 attribute (of the current Search Form) and for each entry in the search results.

The argument should be within a <script> tag with the language set to text/javascript (or a scripting type that supports a compatible syntax). Access Presence generates parameter values that are escaped for Javascript string content. The call has the following format:

func(index, objectClass, href, attName, attVal, objDisplayName, attDisplayName)

Where the output depends on the setting of the configuration-file parameter $\underline{webShow}$ and Search Form settings:

- func value of the useScript parameter
- index incremental index of entries in the search result 0..n
- objectClass the object class of the search result entry
- href-HREF of search result entry
- attName attribute name
- attVal attribute value
- objDisplayName the display name defined for the object class
- attDisplayName the display name defined for the attribute type

alwaysFormat

When this argument is on, the formatting information is generated for all row1 attributes, even when there are no values for the current attribute in the current search result entry. The default behaviour will only generate formatting information when values exist.

By default, this argument is set to off.

format

This argument identifies a set of format directives in the <u>format file</u> to be used to generate the Search Result.

<VFQueryFields>

This tag is replaced by a brief summary of the user's input.

For example, if the user enters sherma in the surname search field and an a in the givenName search field, the output will be as follows:

surname="sherma" & givenName="a"

<VFBanner>

This tag is replaced by the contents of the 'Search Banner' box in the Banners tab of the ViewDS Management Agent (see the help topic *View or modify DUA banners*). This value is stored in the search-banner argument of the operational attribute <u>duaBanners</u>.

NOTE: This tag can also be used in three other templates – Welcome, Search Form and Expanded Entry. In each, the tag is replaced by a different message.

<VFRelatedEntryInput [format=*CHAR]>

During the <u>related-entry workflow</u>, Access Presence replaces <code>VFRelatedEntryInput</code> with an HTML <code>INPUT</code> tag and assigns it a name and value. All attributes declared within the <code>VFRelatedEntryInput</code> tag are copied to this replacement <code>INPUT</code> tag.

For example, the following tag would be replaced by an INPUT tag with an image:

<VFRelatedEntryInput type="image" src="../icons/b_new.gif">

The format attribute references a set of formatting directives in the <u>format file</u>. Only the StartEntry and EndEntry directives are available for this tag.

<VFRelatedEntryForm> </VFRelatedEntryForm>

This tag block is of use in a Search Results template defined specifically for the <u>related-entry</u> workflow.

The related-entry workflow can use either the normal Search Results template or a Search Results template developed specifically for the workflow. The tag block is ignored when it appears in a Search Results template and it is not currently being used in the related-entry workflow. This allows the same Search Results template to be used for the workflow and normal operation.

The tags within the block provide the links required by the workflow to allow the user to add a new role or entry. The links are 'add alternative class' and 'add new entry'.

Examples

The following example results in an Add button being displayed next to each entry in the Search Results page. The Add button invokes the Modify page, which allows the user to associate the alternative class (such as an organizationalRole) with an entry.

```
<VFRelatedEntryForm>
<VFSearchResults>
</VFRelatedEntryForm>
```

NOTE: The above example does not work for Microsoft Internet Explorer (IE). This is because the VFSearchResults tag is replaced by an INPUT tag with its TYPE argument set to IMAGE. With IE, the button does not submit a value, but rather the coordinates of the mouse-click on the image.

The following example results in a New button being displayed below the list of entries. This button also invokes the Modify page, but this time allows the user to add a new entry of the same class as the entries listed on the Search Results page.

```
<VFRelatedEntryForm>
<VFSearchResults>
New Staff Entry <VFRelatedEntryInput type="image" src="../icons/b_
new_entry.gif">
</VFRelatedEntryForm>
```

```
<VFQueryURI [ template=*CHAR ] [ filterfor=*CHAR ]
[ scope=user|base|*CHAR ] [ escval=on|off ] [ id=*CHAR ]
[ pageSize=*DIGIT ] [ reverse ] [raw ]>
```

This tag is replaced by a URL that allows the user to resubmit the search request. The URL reproduces the search request that generated the results currently displayed on the Search Results page.

The tag's arguments are described below.

template	Identifies the name of a Search Result template in the extra template file
filterfor	Restricts the resubmitted search to a specified space-separated list of object classes. This argument overrides the Search Object Classes field in the Search Form. (See the ViewDS Management Agent help topic <i>View or modify a Search Form</i> .)
scope	The <u>scope</u> argument changes the scope of the resubmitted search. Unless restricted searches are required, this argument should be set to 'base'.
escval	When this argument is on, the value generated by the tag is 'escaped' to make it safe for use as a URI.
id	See Common tags and arguments.
pageSize	Sets the number of entries displayed on the Search Results page after the user has resubmitted a search request. When this argument is used, the <u>Tags for</u> <u>navigating multiple Search Results</u> can be implemented to allow navigation between pages of results.
reverse	Indicates that the contents of the Search Results page should be displayed in reverse order when the user clicks the link generated by this tag.
raw	Indicates that a resubmitted search request should use the original search criteria, ignoring any modifications made by the remaining VFQueryURI arguments.

Tags for navigating multiple Search Results

The following tags are replaced by HTML hypertext links that allow users to navigate multiple Search Results pages:

- VFQueryFirstHref replaced by a link to the first page in a set of search results
- VFQueryLastHref replaced by a link to the last page
- VFQueryNextHref replaced by a link to the next page
- VFQueryPreviousHref replaced by a link to the previous page

The tags have the same arguments as the <u>VFQueryURI</u> tag, except for the <u>html</u> argument.

The number of entries on each page is defined by the <code>pageSize</code> argument. If <code>pageSize</code> is undefined, then an input field from the Search Form can be used to set the number entries on each page. If the pageSize cannot be determined, then the above tags produce no output.

URIs produced

The URIs produced by the above tags encode page information in a query string using four attributes:

- before_count identifies the number of entries to display before the target entry
- after_count identifies the number of entries to display after the target entry
- content count identifies the number of entries in the set of results
- target_offset identifies the offset of the target entry to display in the result set. This attribute should normally have a value in the range of 1 to content_count.

The content_count and target_offset attributes are used as a guide. If the actual result set is a different size to the number indicated by content_count then the target_offset value is scaled to reference an entry in the same relative position in the result set. Where the result set size is not known, the first page of results may be referenced by setting target_ offset to 0 and content_count to 1 and the last page of results may be referenced by setting the target_offset to equal content_count.

The content_count should always be set to greater than or equal to 1.

Expanded Entry template

The Expanded Entry template generates the page that presents the details of an individual entry. The Expanded Entry includes the full DN of the entry, all associated attributes (unless nonprintable or hidden), and a list of the subordinate entries in the Directory Information Tree.

NOTE: The configuration-file parameter <u>webTemplAttribute</u> allows alternative Expanded Entry templates to be invoked for specific directory entries. The <u>extra template</u> <u>file</u> allows alternative Expanded Entry templates to be invoked for all users. This subsection describes the tags that can be included in the Expanded Entry template:

- Core template tags
- Target object tags
- Alternative hierarchy tags
- <u>Approval process tags</u>

Core template tags

```
<VFExpandDN [useScript=1*CHAR] [reverse=on|off]
[superioronly=on|off] [fromdepth=1*DIGIT] [format=1*CHAR]
[id=*CHAR]>
```

This tag is replaced by the full DN of the entry.

By default, the DN is displayed in rows, each containing one RDN as an 'attribute-value' pair. Each RDN has a HTML reference attached, which a user can click in order to view the RDN's entry.

For example, in plain text the name { C "AU"/ O "Deltawing" } would be displayed as follows:

```
Country AU
Organization Deltawing
```

In HTML it is:

```
Country <a href="http://host:port/view500/webdua.cgi?ea0_lfz99_
120.&&c=AU">AU</a>
Organization <a href="http://host:port/view500/webdua.cgi?ea0_lfz99_
120.&&o=Deltawing,c=AU">Deltawing</a>
```

useScript

This argument invokes a call to a script function that displays a DN. The script function is identified by the argument's value, and it is invoked for each component of the DN.

The argument should be within a <script> tag with the language set to

text/javascript (or a scripting type that supports a compatible syntax). Access Presence generates parameter values that are escaped for JavaScript string content.

The call has the following format:

```
func(level, objectClass, href, attName, attVal, leaf, objDisplayName,
attDisplayName)
```

Where:

- func value of the useScript parameter
- level level of AVA in DN (int 1..n)
- objectClass the object class of the entry described by the complete DN (this is a string and is the same for every AVA)

- href HREF of the DN down to the current level
- attName attribute name
- attVal attribute value
- leaf indicates whether the entry can have subordinates (True) or not (False)
- objDisplayName the display name defined for the object class
- attDisplayName the display name defined for the attribute type

reverse

This argument generates RDNs in reverse order. Default (off) is to start with the entry under the root.

superioronly

When this argument is specified, the last RDN is not included in the generated information.

The default is off.

fromdepth

This argument declares an integer depth to begin generating DN information. The RDNs from the root down to depth minus one are ignored.

format

This argument identifies a set of format directives in the <u>format file</u> to be used to generate the DN information.

id

This argument is common to many tags (see Common tags and arguments).

<VFExpandAtt [useScript=1*CHAR] [alwaysFormat=on|off] [id=*CHAR] [format=1*CHAR] [dnformat=1*CHAR] >

This tag is replaced by all attributes (except 'hidden' ones) associated with the entry.

By default, the attributes are shown in rows, and long lines are wrapped where necessary. Icons and attribute labels may be attached depending on the configuration-file parameter <u>webShow</u>.

If the user clicks a non-string attribute, a special 'download' message is displayed and the user can save the attribute to disk. For example, the attributes telephoneNumber and userCertificate would be displayed as follows:

```
Phone +61 3 9234 5678
User Certificate press here to download
```

useScript

This argument invokes a call to a script function for each attribute in the entry. The argument's value corresponds to the name of the script function.

The argument should be within a <script> tag with the language set to text/javascript (or a scripting type that supports a compatible syntax). Access Presence generates parameter values that are escaped for JavaScript string content. Access Presence generates a call with the following format:

```
func(objectClass, attName, attVal, objDisplayName, attDisplayName)
....
```

Where:

- func value of the useScript argument
- objectClass the object class of the entry
- attName attribute name
- attVal attribute value
- objDisplayName the display name defined for the object class
- attDisplayName the display name defined for the attribute type

alwaysFormat

When this argument is on, formatting information is generated for all attributes even if the attribute does not have a value in the current entry. When the argument is off (the default), formatting information is only generated when a value exists.

id

This argument is common to many tags (see Common tags and arguments).

format

This argument identifies a set of directives in the <u>format file</u> used to display an attribute.

dnformat

This argument identifies a set of directives in the format file used to display a DN.

```
<VFExpandSubclass [useScript=1*CHAR] [ alwaysFormat = yes|no]
[format=1*CHAR] [show=none|nonleaf|all] [id=*CHAR] [scope= {user |
base | *CHAR}]>
```

This tag is replaced by the entries one level below the current entry in the DIT. These subordinate entries are displayed row-by-row and grouped by their object class.

The default appearance of the subordinate entries is controlled through either:

- ViewDS Management Agent in the Subordinate area of the object class's Properties window (see the help topic *View or modify an object class's DUA presentation*).
- Stream DUA in the sub-classes component of the operational attribute objectClassPresentation.

The above settings can be overridden by the configuration-file parameter <u>webshow</u> and by the search options on the Search Form (see <u>VFSearchOptions</u>).

useScript

This argument invokes a call to a script function that displays a subordinate entry. The script function is identified by the argument's value, and it is invoked for each subordinate entry.

The argument should be within a <script> tag with the language set to text/javascript (or a scripting type that supports a compatible syntax). Access Presence generates parameter values that are escaped for Javascript string content.

Access Presence generates calls that have the following format:

func(index, objectClass, href, attName, attVal, leaf, objDisplayName, attDisplayName)

If <u>webshow</u> is set to sub, or the equivalent setting is selected on the Search Form, then:

- func value of the useScript argument
- objectClass the object class of the subordinate entry
- href-HREF of the subordinate entry
- attName attribute name of RDN
- attVal attribute value of RDN
- leaf indicates whether the entry is a branch (False) or leaf (True)
- objDisplayName the display name defined for the object class
- attDisplayName the display name defined for the attribute type

For any other setting of <u>webshow</u>, the above apply, except for attName and attVal:

- attName attribute name
- attVal attribute value

alwaysFormat

When this argument is on, formatting information is generated for all subclasses, even when there are no subordinates for the subclasses in the current entry. When the argument is off (the default), formatting information is only generated when values exist.

format

This argument identifies of a set of format directives in the <u>format file</u> used to display subclass information.

show

This argument overrides the current behaviour defining which subordinate entries are displayed. This behaviour is defined by the configuration-file parameter <u>webshow</u> and may be modified through the search options on the Search Form.

The argument overrides the current behaviour as follows:

- none do not show any subordinate entries
- nonleaf show only non-leaf subordinate entries
- all show all subordinate entries

id

This argument is common to many tags (see Common tags and arguments).

scope

This argument is common to many tags (see Common tags and arguments).

<VFBanner>

This tag is replaced by the following strings which are concatenated and displayed above the entry's details:

- the label declared for the entry's object class (for example, 'Name')
- the entry's commonName attribute or, if declared, the object class's preferred name
- if declared, the display name and value of the special attribute for the entry's object class

The special attribute allows alternative information to be displayed and might be, for example, the entry's telephone number or photograph.

To illustrate, if:

- · label equals 'Name:'
- preferred name is not set
- special attribute is set to emailAddress (display name is 'Email')

Then the following would be displayed for an example entry:

Name: "Bill Bailey" Email bill.bailey@cheeseworld.com.au

And if:

- label equals 'Staff Number:'
- preferred name is set to employeeNumber
- special attribute is not set

Then the following would be displayed for the same example entry:

Staff Number: "109378777"

NOTE: This tag can also be used in three other templates – Welcome, Search Form, Search Results. In each, the tag is replaced by a different message.

Declaring the label

The label can be declared through either:

- ViewDS Management Agent set in the 'Label' box in the DUA Presentation tab of the object class properties window. See the help topic *View or modify an object class's DUA presentation*.
- Stream DUA set in the exp-name-label component of the operational attribute objectClassPresentation.

Declaring a preferred name

The preferred name can be declared through either:

• ViewDS Management Agent – set in the 'Preferred name' box in the DUA Presentation tab of the object class properties window. See the help topic *View or modify an object class's DUA presentation*.

• Stream DUA - set in the preferredName component of the operational attribute objectClassPresentation.

Declaring the special attribute

The label can be declared through either:

- ViewDS Management Agent set in the 'Name' box in the DUA Presentation tab of the object class properties window. See the help topic *View or modify an object class's DUA presentation*.
- Stream DUA set in the special-att component of the operational attribute objectClassPresentation.

<VFAssPassFormHref [html=1*CHAR] [id=*CHAR]>

This element is replaced by a hypertext link to the Assign Password page. Access to the Assign Password page is not part of the default Access Presence configuration. To allow access, add this tag to the Expanded Entry template.

The html and id arguments are common tags and arguments.

<VFLabel>

An alternative label to the information displayed by the <u>VFBanner</u> tag.

It is replaced by the value of the mandatory naming attribute (defined by schema) for the current entry. Alternatively, if defined, a 'preferred name' is displayed (see preferredName).

Target object tags

These tags are replaced by hypertext links to the <u>target-object cache templates</u>. For a description of the target-object cache, see page $\underline{1}$.

The configuration-file parameter $\underline{webTargetObject}$ controls whether these links are displayed to all users.

```
<VFSetTargetObjHref [confirm] [html=1*CHAR] [id=*CHAR]>
```

This tag is replaced by a hypertext link that empties the target-entry cache and then adds the current entry to it.

The confirm, html and id arguments are described in Common tags and arguments.

<VFShowTargetObjHref [html=1*CHAR] [id=*CHAR] [expandSingle= on|off] >

This tag generates a link that displays the content of the target-object cache. Its behaviour changes according to the number of entries in the target-object cache:

Target objects	Tag is replaced by a link to
None	Base object
One	Target object
Multiple	Show Target Objects page

However, if the expandSingle argument is present and set to off, then the tag generates a link to the <u>Show Target Objects</u> page. If the argument is absent or set to on, and there is a single entry in the target-object cache, then the tag generates a link to the Expanded Entry page.

The html and id arguments are described under Common tags and arguments.

<VFMoveHref [confirm] [html=1*CHAR] [id=*CHAR]>

This tag generates a link that moves the current entry to below a new superior within the directory hierarchy. Its behaviour differs according to the number of entries in the target-object cache:

Target objects	Tag is replaced by a link that
None	Moves the current entry so that it becomes an immediate subordinate of the target object. The confirm argument invokes a confirmation dialog before the entry is moved.
One	Opens the <u>Select Target Object</u> page, which allows the user to select a new superior for the current entry.

The html and id arguments are described under Common tags and arguments.

<VFImportHref [confirm] [html=1*CHAR] [id=*CHAR]>

This tag generates a link that imports entries from within the directory hierarchy so that they become subordinate to the current entry. Its behaviour differs according to how many entries are in the target-object cache:

Target objects	Tag is replaced by a link that
None	Moves the target object to be an immediate subordinate of the current entry. The confirm argument invokes a confirmation dialog before the entry is moved.
One	Opens the <u>Select Entries to Import</u> page, which allows the user to select the entries to become subordinates of the current entry

The html and id arguments are described under Common tags and arguments.

Access Presence only generates a link for this tag if one of the following applies:

- the user has super-user privileges
- moveMultipleSubs is enabled through either the ViewDS Management Agent (see help topic View or modify default entitlements for DUA users) or through the Stream DUA in either defaultEntitlement or userEntitlement.

The html and id arguments are described under Common tags and arguments.

<VFRemovalsHref [html=1*CHAR] [id=*CHAR]>

This tag generates a link to the <u>Select Entries to Remove template</u> to select and delete multiple entries in the target object cache in a single operation.

The html and id arguments are described under Common tags and arguments.

Alternative hierarchy tags

These tags relate to the alternative hierarchies.

```
<VFExpandAltSubord type=AttributeName [ useScript=1*CHAR ]
[ alwaysFormat=yes|no ] [ format=1*CHAR ] [ scope= {user | base |
*CHAR} ] [ show=none|nonleaf|all ] [ id=*CHAR ] >
```

This tag displays an alternative hierarchy of entries below the current entry. It provides an alternative to the standard DIT hierarchy provided by the VFExpandSubclass tag.

The alternative hierarchy is based on the attribute identified by the t_{ype} argument. For example, if t_{ype} were set to manager, all entries whose manager attribute is set to the DN of the current entry would be displayed. This would be irrespective of where they appear in the DIT.

Except for type, this tag's arguments are identical to those described under <u>VFExpandSubclass</u>. The type argument identifies a DN-type attribute.

```
<VFAltAddHref type=AttributeName [ confirm ] [ html=1*CHAR ]
```

[id=*CHAR]>

This tag generates a link to the Select Entries to Add to Alternative Hierarchy template.

Access Presence does not always replace the VFAltAddHref tag with a link. It will only display a link if:

- the schema and access controls allow the user to add the entries in the target-object cache to the alternative hierarchy
- the entries in the target-object cache are not currently in the alternative hierarchy

The confirm, html and id arguments are common tags and arguments.

<VFAltMoveHref type=AttributeName [confirm] [html=1*CHAR] [id=*CHAR]>

This tag generates a link to the <u>Select Entries to Move in Alternative Hierarchy template</u>. Access Presence will only display the link if:

- the schema and access controls allow the user to move the entries in the target-object cache to the alternative hierarchy
- the entries in the target-object cache are already in the alternative hierarchy

The confirm, html and id arguments are common tags and arguments.

<VFAltRemoveHref type=AttributeName [confirm] [html=1*CHAR]</pre>

[id=*CHAR]>

This tag generates a link that removes the current entry from the alternative hierarchy identified by the VFExpandAltSubord tag's type parameter.

Access Presence will only display the link if:

- the user has appropriate permissions to remove the entry
- the current entry is in the alternative hierarchy

The confirm, html and id arguments are <u>common tags and arguments</u>.

<VFAltExpandHref type=AttributeName [html=1*CHAR] [id=*CHAR]>

This tag generates a link to display the current entry's subordinates within an alternative hierarchy. Access Presence will only display the link if the current entry has subordinates within the alternative hierarchy identified by the VFExpandAltSubord tag's type parameter.

The confirm, html and id arguments are common tags and arguments.

Approval process tags

These tags should be added to the Extended Entry template in order to implement the <u>approval</u> <u>process</u>. The links and information they generate is only displayed to users with appropriate access rights.

<VFRequestDeleteHref [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a hypertext link to the Request Remove Entry template.

The html and id arguments are described under Common tags and arguments.

<VFRequestAddSubHref [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a hypertext link to the Add page, which allows the user to submit a request to add a subordinate to the current entry.

The html and id arguments are described under Common tags and arguments.

<VFRequestModifyHref [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a hypertext link to the Modify page, which allows the user to submit a request to modify the current entry.

The html and id arguments are described under Common tags and arguments.

<VFRequestMoveHref [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a link that submits a request to move the current entry.

The html and id arguments are described under Common tags and arguments.

<VFRequestImportHref [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a link that submits a request to import entries from within the directory hierarchy so that they become subordinate to the current entry.

The html and id arguments are described under Common tags and arguments.

<VFRequestRemovalsHref [html=1*CHAR] [id=*CHAR]>

This tag generates a link to the <u>Select Entries to Remove template</u> to select and request the deletion multiple entries in the target object cache in a single operation.

It is suitable for users that do not have permission to remove any entries in the target object cache but do have permission to submit a request to remove at least one of these entries.

The html and id arguments are described under Common tags and arguments.

<VFRequestList [id=*CHAR] [caption=*CHAR]>

This tag is replaced by an HTML table of update requests that relate to the current user and are awaiting approval.

The table contains the following information:

- Requestor a hypertext link to the Expanded Entry page for the user who requested the update.
- Status the status of the update request.
- Type the type of update (such as modify, delete or move an entry).
- Time the timestamp when the request was submitted.
- Reason the reason for the update entered by the requestor.
- Action a hypertext link to the page allowing the approver to view and either reject or approve the request.

The caption argument can be used to declare the text in an HTML caption in the table generated by this tag. If the argument is undeclared, or is an empty string, then no HTML caption is generated in the table.

The id argument is described under Common tags and arguments.

<VFRequestHistory [id=*CHAR] [caption=*CHAR]>

This tag is replaced by an HTML table containing the list of activities that have occurred on the current update request. It only generates output when the user is reviewing an update request.

The caption argument can be used to declare the text in an HTML caption in the table generated by this tag. If the argument is undeclared, or is an empty string, then no HTML caption is generated in the table.

The id argument is described under Common tags and arguments.

Error template

The Error template generates a page that displays ViewDS error messages. The following tags are available in the Error template.

<VFErrorStr [format=1*CHAR]>

This tag is replaced with the unformatted error string if an error has occurred. For the possible error strings, with error numbers, see VFHasError below.

The format argument is used to identify <u>format file</u> specification that displays the error string in a format appropriate to its context. (The specification should use the key words <code>StartEntry and EndEntry.)</code>

<VFHasError>

This tag is replaced by a '0' if there is no error present, or by an error number. Each error number has a corresponding error string, which replaces <VFErrorStr> described above.

Error number	Error string
12127	Sorry, at least %s characters are required for the input.
16001	Sorry, no word match for %s. Please re-enter.
16014	Cannot connect to the Directory. The Directory or the network may be down. Please try again later.
16016	The search has identified too many entries. Please be more specific.
16017	The request has timed out. Please retry later.
16019	Server busy. Please retry later.
16020	Sorry, the directory does not have sufficient resources to process this request.
16021	The entry has been moved or deleted by another user.
16022	No matching entry could be found.
16024	Corrupted entry detected. Please report this to your administrator.
16025	Your Search/Read has been rejected by the server.
16026	You do not have sufficient access permission to do this operation.
16027	The entry has been modified by another user.
16028	The Directory does not accept duplicate values.
16029	The entry already exists.
16030	The operation is not allowed on non-leaf node.
16037	Sorry, please give a name to the new entry.

The error numbers and corresponding error strings are as follows. Several error strings include $\$ s', which is replaced by appropriate text.

Error number	Error string
16048	A system level error has been detected. Please report this to your administrator.
16049	Unexpected Error. Please report the following number to your administrator:
16126	Sorry, an invalid/non-printable character has been detected in field %s. Please remove the character and retry.
16128	Sorry, field %s is too long.
16129	Sorry, only single value is allowed for %s.
16130	Sorry, a non-unique value is detected in field %s. Please remove any non- unique value in the field.
16131	Sorry, the phone number %s entered is invalid. Please re-enter.
16132	Sorry, please fill in the mandatory field %s .
16133	Sorry, the time you entered in field %s is invalid. Please re-enter the time.
16134	Sorry, your input for field %s is of an invalid format. Please re-enter the field.
16135	Sorry, the OR Address you entered is invalid. Please re-enter.
16151	Your Username and/or Password is incorrect. Please check them before trying to login again.

Modify template

The Modify template generates a page that allows a user to modify an entry. It also allows a user to enter the details for a new entry, and ensures that the values available for selection conform to schema and access controls.

The following tags are only outputted if the user has the required privileges.

```
<VFModifyHref [confirm] [html=1*CHAR] [id=*CHAR]>
```

This tag is replaced by a hypertext link to the Modify page, which allows the user to modify the current entry.

The confirm, html and id arguments are described under <u>Common tags and</u> arguments.

```
<VFModifyForm [id=*CHAR] name=1*CHAR [summary=1*CHAR]>
```

This tag block is replaced by an HTML FORM element and should contain the VFModifyAtt tag.

For example:

```
<VFModifyForm id="modform" name="modform" summary="Modify">
<caption><h4>Modify details for<VFLabel></h4></caption>
<VFModifyAtt width="36"><VFErrorStr>
```

```
</VFModifyForm>
```

The id argument is described under Common tags and arguments.

```
<VFModifyAtt [width=1*DIGIT] [id=*CHAR] [format=*CHAR]
[description={row | heading | data}] [save = {top | bottom | both}
[checkbox[=1*CHAR]]>
```

This tag is replaced by modifiable input controls containing an entry's attribute values. It should be included in the code block <VFModifyForm> </VFModifyForm>.

An attribute with a Distinguished Name syntax is displayed in a list box unless the optional checkbox argument is included (see below):

- a single-valued attribute is displayed in a single-select list box
- a multi-valued attribute is displayed in a multiple-select list box

In both cases, the user can select an empty option. The content of the list box is sorted alphabetically according to the values generated by the VFLabel tag.

The entries in the target-object cache are presented in a single-select list box.

The format and id arguments are described under Common tags and arguments.

The width argument specifies the width of the input boxes for attribute values (the default is 50).

save

This argument controls whether the Save button is displayed above, below, or both above and below the form's data. The default is top.

description

This argument controls which part of a row responds to the user's mouse hovering over it. The response is to display the description defined in the attribute's DUA presentation – see the ViewDS Management Agent help topic *View or modify an attribute's DUA presentation*.

The description argument can have one of the following values:

- row the entire row (the default) responds to the mouse
- heading the heading cell of the row responds to the mouse
- data the input field responds to the mouse

checkbox

This argument indicates that a multi-valued attribute is displayed using checkbox input fields, rather than a multiple-select list box. This occurs only for multi-valued attributes whose permitted values are well-defined, either through a constrained syntax, enumerated type or the use of pre-processing functions. It also occurs for the auxiliary object class list.

The checkbox input fields are generated for each possible value of the attribute. These are all contained within a FIELDSET HTML element. The checkbox has an optional value. If

this value is provided, it will be used as a value for the class attribute of the FIELDSET HTML elements generated on the Modify form.

<VFDeleteHref [confirm] [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a hypertext link that deletes the current entry. The confirm argument invokes a confirmation dialog when the link is clicked by a user.

The html and id arguments are described under Common tags and arguments.

Modify Value Form template

The Modify Value Form template generates a page that allows a user to add, modify and delete individual values of a multi-value attribute. It also ensures that the values available for selection conform to schema and access controls.

The following tags are only outputted if the user has the required privileges.

```
<VFModifyForm [id=*CHAR] name=1*CHAR [summary=1*CHAR]>
```

This tag block is replaced by an HTML FORM element and should contain the ${\tt VFModifyVal}$ tag.

For example:

```
<VFModifyForm id="modform" name="modform" summary="Modify">
<caption><h4>Modify details for<VFLabel></h4></caption>
<VFModifyVal width="36"><VFErrorStr>
</VFModifyForm>
```

The id argument is described under Common tags and arguments.

```
<VFModifyVal [width=1*DIGIT] [id=*CHAR] [format=*CHAR]
[description={row | heading | data}] [save = {top | bottom | both}
[checkbox[=1*CHAR]]>
```

This tag is replaced by modifiable input controls containing values. It should be included in the code block <VFModifyForm> </VFModifyForm>.

An attribute with a Distinguished Name syntax is displayed in a multiple-select list box unless the optional checkbox argument is included (see below).

The user can select an empty option. The content of the list box is sorted alphabetically according to the values generated by the <u>VFLabel</u> tag.

The entries in the target-object cache are presented in a single-select list box.

The format and id argument is described under Common tags and arguments.

The width argument specifies the width of the input boxes for attribute values (the default is 50).

save

This argument controls whether the Save button is displayed above, below, or both above and below the form's data. The default is top.

description

This argument controls which part of a row responds to the user's mouse hovering over it. The response is to display the description defined in the attribute's DUA presentation – see the ViewDS Management Agent help topic *View or modify an attribute's DUA presentation*.

The description argument can have one of the following values:

- row-the entire row (the default) responds to the mouse
- heading the heading cell of the row responds to the mouse
- data the input field responds to the mouse

checkbox

This argument indicates that a multi-valued attribute is displayed using checkbox input fields, rather than a multiple-select list box. This occurs only for multi-valued attributes whose permitted values are well-defined, either through a constrained syntax, enumerated type or the use of pre-processing functions. It also occurs for the auxiliary object class list.

The checkbox input fields are generated for each possible value of the attribute. These are all contained within a FIELDSET HTML element. The checkbox has an optional value. If this value is provided, it will be used as a value for the class attribute of the FIELDSET HTML elements generated on the Modify Value form.

<VFAddValueInput [html=1*CHAR]>

This tag must be used within the scope of the HTML form created using the VFModifyForm tag.

It will generate a submit button on the Modify Value form suitable for adding a new value if the current user has permission to add a value for the attribute.

This tag produces an HTML input control with both type and name attributes. If an optional "html" parameter is present, the remainder of the control, including the closing '>' for the element, are provided by this parameter. Otherwise, the value and title attributes are provided with default values.

<VFModifyValueInput [html=1*CHAR]>

This tag must be used within the scope of the HTML form created using the VFModifyForm tag.

It will generate a submit button on the Modify Value form to modify the current value if the current user has permission to modify the value of the attribute.

This tag produces an HTML input control with both type and name attributes. If an optional "html" parameter is present, the remainder of the control, including the closing '>' for the element, are provided by this parameter. Otherwise, the value and title attributes are provided with default values.

<VFDeleteValueInput [html=1*CHAR]>

This tag must be used within the scope of the HTML form created using the VFModifyForm tag.

It will generate a submit button on the Modify Value form to delete the current value if the current user has permission to delete the value of the attribute.

This tag produces an HTML input control with both type and name attributes. If an optional "html" parameter is present, the remainder of the control, including the closing '>' for the element, are provided by this parameter. Otherwise, the value and title attributes are provided with default values.

<vFPreprocessInput [html=1*CHAR]>

This tag must be used within the scope of the HTML form created using the VFModifyForm tag.

It will generate a checkbox input control that can be used to enable/disable optional preprocessing for a value of an attribute. The input control will only be generated when preprocessing is applicable for the value. Preprocessing cannot be applied to attributes with complex syntax, such as annotated types.

This tag produces an HTML input control with both type and name attributes. If an optional "html" parameter is present, the remainder of the control, including the closing '>' for the element, are provided by this parameter. Otherwise, the id, value and title attributes are provided with default values.

Add template

The Add template generates a page that allows the user to select the object class for a new entry.

<VFAddSubHref [confirm] [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a hypertext link to the Add page.

The confirm, html and id arguments are described under <u>Common tags and</u> arguments.

<VFAddOCSel>

This tag is replaced by a list box containing all the available entry types (object classes) that the user can create under the current entry.

It should be used within a FORM block which has an ACTION parameter value generated by VFAddOCURI (see below).

<VFAddOCURI [id=*CHAR]>

This tag is replaced by a URI pointing to the Modify page from the Add page.

It should be used to generate the ACTION parameter value for a FORM containing the VFAddOCSel tag.

The id argument is described under Common tags and arguments.

Print Form template

The Print Form template generates a page that allows the user to request a report. The list of available reports is configured through the printconfig file (see <u>Configuring for printing</u>).

A requested report is generated by the <u>Printing DUA</u>, and the results are displayed according to the <u>MIME mapping file</u>. If no MIME type is set for the report in the <u>printconfig</u> file then the report will be displayed by the <u>Print template</u>.

<VFPrintFormHref [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a hypertext link to the Print Form page.

The html and id arguments are described under Common tags and arguments.

<VFPrintSelection [width=1*DIGIT] [useScript=1*CHAR] [scope= {user | base | *CHAR}]>

This tag is replaced by the dialog that allows a user to select a report to be printed. The width argument specifies the width of the input fields in the selection dialog.

The input arguments are:

- The print report type, a list box of the print scripts available to the user, as defined in the printconfig file (see Configuring for printing).
- The base entry from which to generate the report. The presents a drop-down list containing the entries in the target-object cache (see <u>Target-object cache templates</u>). If the user does not select an entry, the report's base entry will be the one defined in the print script.
- Optionally, the *output file name*. If this is not provided, the report will only be displayed to the screen.

This tag can be used in any other template to display the list of reports with hypertext links to each. When used in a template other than the Print Form, however, it can only be invoked using the useScript argument. If used in the Welcome template, the scope argument must be set to base.

useScript

This argument generates a call to a script function identified by the argument's value.

The argument should be within a <script> tag with the language set to text/javascript (or a scripting type that supports a compatible syntax). Access Presence generates parameter values that are escaped for JavaScript string content.

The call has the following format:

func(id, label, base, entry, url)

Where:

- func the value of the useScript argument
- id an integer that identifies a print script by its position in the printconfig file
- label a string that identifies a print script by its name in the printconfig file

- base the LDAP string encoding for the DN of the base entry from which the report will be generated
- url the URL required to access the report

scope

This argument allows you to change the scope of a report. By default the scope of a report is the current entry and its subordinates.

The scope argument is described under Common tags and arguments.

Print template

The Print template generates a page to present the report requested through the Print Form page.

<VFPrintReport >

This tag is replaced by the generated report.

New Password template

The New Password template allows a user to change their password – the user enters their current password and then a new password twice.

<VFChangePassFormHref [html=1*CHAR] [id=*CHAR]>

This tag is replaced by a hypertext link to the New Password page.

The html and id arguments are described under Common tags and arguments.

<VFChangePassURI [id=*CHAR]>

This tag is used to construct a URI to submit the New Password page. It should be used to generate the ACTION parameter value for a FORM containing the VFAuthOUserPassID, VFAuthUserPassID and VFAuthUserPassID2 tags.

<FORM METHOD="post" ACTION="<VFChangePassURI>">

The id argument is described under Common tags and arguments.

<VFAuthOUserPassID>

This tag is the value of the name field in the HTML input tag for the user's current password:

<input name="<VFAuthOUserPassID>" type="password" size="10">

The ${\tt type}$ field should be set to password so that the user's password is not displayed on the screen.

<VFAuthUserPassID>

This tag is the value of the name field in HTML input tag tag for the user's new password: <input name="<VFAuthUserPassID>" type="password" size="10">

The type field should be set to password so that the user's password is not displayed on the screen.

<VFAuthUserPassID2>

This tag is the value of the name field in the HTML input tag for the user's confirmed password:

<input name="<VFAuthUserPassID2>" type="password" size="10">

The type field should be set to password so that the user's password is not displayed on the screen.

<VFAuthReferer>

This tag ensures that Access Presence returns to the page the user was attempting to view before resetting their password.

The tag is replaced by an HTML input element:

<input type=`hidden' name=`referrer' value=URL>

The value is equal to the URL for the page the user was attempting to view.

Assign Password template

The Assign Password template allows a user to assign or change the user name and password of another user. It is subject to the access controls that apply to the user attempting to access the page.

NOTE: To provide access to the Assign Password page, a link to the page must be added to the Expanded Entry template (see <<u>VFAssPassFormHref</u>>).

The VFAuthUserPassID and VFAuthUserPassID2 fields are described under the <u>New</u> Password template.

<VFAssPassTable>

This tag is replaced by an HTML table containing all the input fields required for the Assign Password page. The fields include the current user name and password.

The tag must be within an HTML form element that has an action provided by the VFAssPassURI template tag. Any text included between the VFAssPassTable tag's name and closing '>' is included as an attribute of the generated HTML table element's start tag.

```
<form method="post" action="<VFAssPassURI>">
<VFAssPassTable>
<input type="submit" name="submit" value="Change Password">
</form>
```

<VFAssPassURI [id=*CHAR]>

This tag is replaced by a URI to submit the Assign Password form. It is used to generate the

value for the ACTION element in a FORM containing the VFAssPassTable,

VFAuthUserNameID, VFAuthUserPassID and VFAuthUserPassID2 tags.

<form method="post" action="<VFAssPassURI>">

The id argument is described under Common tags and arguments.

<VFAuthUserNameID>

This tag is the value of the name field in the HTML input tag for the user name of the user whose user name or password are to be changed:

```
<input name="<VFAuthUserNameID>" value="<VFAttVal id=userName>" type="text">
```

The type field should be set to text.

Request Remove Entry template

This template is part of the approval process.

The Request Remove Entry page is invoked by the link generated by the

VFRequestDeleteHref.

For a 'requestor', the page allows the user to enter the reason why they want to delete the current user; and for an 'approver', the page allows the user to view the reason and either reject or approve the deletion.

The Request Remove Entry template should include the following tags enclosed within an HTML FORM element:

- <u>VFRequestReason</u>
- <u>VFRequestSaveInput</u>
- <u>VFRequestCancelInput</u>
- <u>VFRequestApproveInput</u>
- VFRequestRejectInput

The method attribute of the FORM should be set to post and its action attribute set to the output of the VFRequestDeleteURI template file tag (see below).

<VFRequestDeleteURI [html=1*CHAR] [id=*CHAR]>

This tag generates the value of the action attribute in an HTML FORM in the Request Remove Entry template.

The html and id arguments are described under Common tags and arguments.

Global changes templates

These templates allow an Access Presence user to modify attributes globally.

To illustrate, if a user changes an attribute's value globally, then all instances of the attribute (within the scope of the change) will be set to the new value.

Before a user can apply global changes, the ViewDS DSA must be configured to enable this functionality (see <u>Configuring for global changes</u>).

There are three global changes templates:

- Global Change Request template
- Global Change Confirm template
- Global Change Results template

Each is described below.

Global Change Request template

The Global Change Request template presents a form that allows a user to specify a global change.

<VFGCRequestHref html=*CHAR>

This tag provides a link to the Global Change Request page. For example:

<VFGCRequestHref html=">Global Changes">

The html argument is described under Common arguments.

<VFGCRequestURI [id=*CHAR] [html=1*CHAR]>

This tag must be included in the template, and is replaced by a URI to submit the Global Change Request page and display the Global Change Confirm page. It generates the value for the ACTION element in a FORM containing the VFGCRequest tag. The FORM should have its METHOD set to POST, and should include a submit button.

For example:

```
<form method="post" action="<VFGCRequestURI>">
...
<VFGCRequest width="36">
<VFErrorStr format="error">
<input type="image" src="../icons/newface/save.jpg">
...
</form>
```

The id and html arguments are described under Common arguments.

<VFGCRequest [width=1*DIGIT]>

This tag is replaced by form elements that allow the user to specify a global change. The user can select the scope of the change, the entry type and attribute to apply the change to, the nature of the change (add, modify, replace value), the new value, etc.

The width argument specifies the length of the input boxes displayed.

Global Change Confirm

The Global Change Confirm template generates a page showing a summary of the global changes defined in the Global Change Request.

<VFGCConfirmURI [id=*CHAR] [html=1*CHAR]>

This tag must be included in the template, and is replaced by a URI to submit the Global Change Confirm page and display the Global Change Results page. It generates the value for the ACTION element in a FORM containing the VFGCConfirm tag. The FORM should have its METHOD set to POST, and should include a submit button.

For example:

```
<form method="post" action="<VFGCConfirmURI>">
...
<VFGCConfirm width="32">
<VFEcrorStr format="error">
<input type="image" src="../icons/newface/save.jpg">
...
</form>
```

The id and html arguments are described under Common arguments.

<VFGCConfirm [width=1*DIGIT]>

This tag is replaced by a list of the entries, and their attributes, that will be affected by the global changes defined in the Global Change Request. It also displays check boxes to allow the user to confirm each change before they are applied.

The width argument specifies the length of the input boxes displayed.

Global Change Results

The Global Change Results template generates a page that shows whether a global change was successful for each entry it was applied to.

<VFGCResults [id=*CHAR]>

This tag must be included in the template, and is replaced by a list of entries and the status of the global change for each.

The id argument is described under Common arguments.

Target-object cache templates

This subsection describes the tags and templates relating to the <u>target-object cache</u>. The tags that are common to many templates are described under <u>Common target object tags</u>. The tags that can appear in templates and the <u>format file</u> are described under <u>Target object tags</u>.

Common target object tags

These tags only apply to the first entry in the target-object cache. They can appear in any Access Presence template except the Authentication template.

<VFTargetObjStr>

This tag is replaced by a string representation of the DN of the current 'target object'. If no

target object is set, nothing is generated.

<VFTargetObjDN [useScript=1*CHAR]>

This tag is replaced by the LDAP DN of the current target object, if there is one set. This replacement string will be escaped for HTML, with quotes and angle brackets replaced by their character entity reference representations (for example, & is replaced by ").

useScript

This argument generates a call to a script function identified by the argument's value.

The argument should be within a <script> tag with the language set to text/javascript (or a scripting type that supports a compatible syntax). Access Presence generates parameter values that are escaped for Javascript string content.

The call has the following format:

func(ldapDN, objectClass)

Where:

- ldapDN a quoted string containing the LDAP DN of the current target object, escaped appropriately for use as a script string
- objectClass a string representing the object class of the current target object, if available; otherwise an empty string

<VFTargetObjOC>

Deprecated.

Show Target Objects template

This template allows a user to view the contents of, and delete entries from, the target-object cache.

The Show Target Objects page is displayed when a user:

- clicks the link generated by VFShowTargetObjHref tag
- submits a form utilising the ${\tt VFShowTargetObjectsURI}$ tag described below

```
<VFShowTargetObjectsURI [id=*CHAR] >
```

This tag must be included in the template, and is replaced by a URI that submits the Show Target Object page. It generates the value for the ACTION element of a FORM that uses the POST method and contains the VFShowTargetObjects tag. For example:

```
<form method="post" action="<VFShowTargetObjectsURI>">
<input type="checkbox" name="toggle-all" value="true"
onchange="toggle_all(this);">
<input type="checkbox" name="toggle-all" value="true"
onchange="toggle_all(this);">
>unit="true"
onchange="toggle_all(this);">
>unit="true"
onchange="toggle_all(this);">
```

```
<VFShowTargetObjects format="targets"></tFErrorStr format="error">

</nput type="image" src="../icons/newface/delete.jpg">
```

The id argument is described under Common arguments..

<VFShowTargetObjects [format=1*CHAR] [id=*CHAR] >

This tag is replaced by a list of entries in the target-object cache. They are sorted alphabetically according to the values generated by the <u>VFLabel</u> tag.

The VFShowTargetObjects tag must be within an HTML FORM whose ACTION element is set to the VFShowTargetObjectsURI.

The VFShowTargetObjects tag must also include the format parameter to identify a format-file specification which includes the <u>VFSelectTargetObjInput</u> tag. The VFSelectTargetObjInput tag is replaced by HTML INPUT controls (checkboxes) that allow the user to select the entries to be removed from the target-object cache. They are removed when the FORM is submitted.

To illustrate, consider the following VFShowTargetObjects tag:

```
<VFShowTargetObjects format="targets">
```

Its format parameter identifies the following format-file specification:

```
<format * * targets>
<VFSelectTargetObjInput type="checkbox">
<VFSelectTargetObjInput type="checkbox">
```

The id argument is described under Common arguments.

Select Target Object template

This template displays the entries in the target-object cache that are valid potential superiors of the entry being moved within the directory hierarchy. It allows the user to select the new superior.

The Select Target Object page is displayed when a user clicks the link generated by the <u>VFMoveHref</u> tag. That is, if there is more than one entry in the target-object cache that is a valid superior for the entry being moved.

<VFSelectTargetObjURI [id=*CHAR] >

This tag must be included in the template, and is replaced by a URI that submits the Select

Target Object page. It generates the value for the ACTION element of a FORM that uses the POST method and contains the VFSelectTargetObj tag. For example:

The id argument is described under Common arguments.

<VFSelectTargetObj [format=1*CHAR] [id=*CHAR] >

This tag is replaced by a list of entries in the target-object cache that are valid superiors to the entry being moved. They are sorted alphabetically according to the values generated by the <u>VFLabel</u> tag.

The VFSelectTargetObj tag must be within an HTML FORM whose ACTION element is set to the VFSelectTargetObjURI.

The VFSelectTargetObj tag must also include the format parameter to identify a format-file specification which includes the <u>VFSelectTargetObjInput</u> tag. The VFSelectTargetObjInput tag is replaced by HTML INPUT controls (radio buttons) that allow the user to select the entry to be the new superior to the entry being moved. To illustrate, consider the following VFSelectTargetObj tag:

<VFSelectTargetObj format="select">

Its format parameter identifies the following format-file specification:

```
<format * * select>

    <
    <vFSelectTargetObjInput type="radio">

    <
```

The id argument is described under Common arguments.

Select Entries to Import template

This template displays the entries in the target-object cache that are valid subordinates to the current entry. It allows the user to select new subordinates for the current entry.

The Select Entries to Import page is displayed when a user clicks the link generated by the <u>VFImportHref</u> tag.

<VFSelectImportsURI [id=*CHAR]>

This tag must be included in the template, and is replaced by a URI that submits the Select Entries to Import page. It generates the value for the ACTION element of a FORM that uses the POST method and contains the VFSelectImports tag.

The id argument is described under Common arguments.

<VFSelectImports [format=1*CHAR] [id=*CHAR] >

This tag is replaced by a list of entries in the target-object cache that are valid subordinates to the current entry. They are sorted alphabetically according to the values generated by the <u>VFLabel</u> tag.

The VFSelectImports tag must be within an HTML FORM whose ACTION element is set to the VFSelectImportsURI.

The VFSelectImports tag must also include the format parameter to identify a formatfile specification which includes the <u>VFSelectTargetObjInput</u> tag. The VFSelectTargetObjInput tag is replaced by HTML INPUT controls (checkboxes) that allow the user to select the new subordinate entries. The id argument is described under <u>Common arguments</u>.

Select Entries to Remove template

This template displays the entries in the target-object cache that are valid candidates to be removed. It allows the user to select and delete or select and request the deletion of multiple entries in a single operation, depending on their permissions.

The Select Entries to Remove page is displayed when a user clicks the link generated by the <u>VFRemovalsHref</u> tag or the <u>VFRequestRemovalsHref</u> tag.

<VFSelectRemovalsURI [id=*CHAR] >

This tag must be included in the template, and is replaced by a URI that submits the Select Entries to Remove page. It generates the value for the ACTION element of a FORM that uses the POST method and contains the VFSelectRemovals tag.

The id argument is described under Common arguments.

<VFSelectRemovals [format=1*CHAR] [id=*CHAR] >

This tag is replaced by a list of entries in the target-object cache that are valid candidates for removal. They are sorted alphabetically according to the values generated by the $\underline{VFLabel}$ tag.

The VFSelectRemovals tag must be within an HTML FORM whose ACTION element is set to the VFSelectRemovalsURI.

The VFSelectRemovals tag may also include the format parameter to identify a formatfile specification describing how each entry in this list should be displayed. This format-file specification must include the <u>VFSelectTargetObjInput</u> tag. The VFSelectTargetObjInput tag is replaced by HTML INPUT control that is used to identify which entries should be removed when the enclosing HTML FORM is submitted. The id argument is described under Common arguments.

Select Entries to Add to Alternative Hierarchy template

This template allows a user to add entries to an alternative hierarchy. The user selects the entries from the target-object cache to become new subordinates (within the alternative hierarchy) of the current entry.

The Select Entries to Add to Alternative Hierarchy page displays the entries in the target-object cache that are:

- valid possible subordinates within an alternative hierarchy to the current entry
- are NOT currently in the alternative hierarchy

The current entry is the entry displayed by the Expanded Entry page from which this page is invoked by the user – see the <u>VFAltAddHref</u> tag. The alternative hierarchy is identified by the type parameter of the <u>VFExpandAltSubord</u> tag.

<VFAltAddSelectionURI [id=*CHAR] >

This tag must be included in the template, and is replaced by a URI that submits the Select Entries to Add to Alternative Hierarchy page. It generates the value for the ACTION element of a FORM that uses the POST method and contains the VFAltAddSelection tag.

The id argument is described under Common arguments.

<VFAltAddSelection [format=1*CHAR] [id=*CHAR] >

This template displays the entries in the target-object cache that are:

- valid possible subordinates within an alternative hierarchy to the current entry
- are NOT currently in the alternative hierarchy

They are sorted alphabetically according to the values generated by the $\underline{\texttt{VFLabel}}$ tag.

The VFAltAddSelection tag must be within an HTML FORM whose ACTION element is set to the VFAltAddSelectionURI. It must also include the format parameter to identify a format-file specification which includes the <u>VFSelectTargetObjInput</u> tag. The VFSelectTargetObjInput tag is replaced by HTML INPUT controls (checkboxes) that allow the user to select the new subordinate entries.

The id argument is described under Common arguments.

Select Entries to Move in Alternative Hierarchy template

This template allows a user to move entries within an alternative hierarchy. The user selects the entries from the target-object cache to become new subordinates (within the alternative hierarchy) of the current entry.

The Select Entries to Move in Alternative Hierarchy page displays the entries in the target-object cache that are:

- valid possible subordinates within an alternative hierarchy to the current entry
- are already in the alternative hierarchy

The current entry is the entry displayed by the Expanded Entry page from which this page is invoked by the user – see the <u>VFAltMoveHref</u> tag. The alternative hierarchy is identified by the type parameter of the <u>VFExpandAltSubord</u> tag.

<VFAltMoveSelectionURI [id=*CHAR] >

This tag must be included in the template, and is replaced by a URI that submits the Select Entries to Move in Alternative Hierarchy page. It generates the value for the ACTION element of a FORM that uses the POST method and contains the VFAltMoveSelection tag.

The id argument is described under Common arguments.

<VFAltMoveSelection [format=1*CHAR] [id=*CHAR] >

This tag is replaced by a list of entries in the target-object cache that are:

- valid possible subordinates within an alternative hierarchy to the current entry
- are already in the alternative hierarchy

They are sorted alphabetically according to the values generated by the $\underline{VFLabel}$ tag.

The VFAltMoveSelection tag must be within an HTML FORM whose ACTION element is set to the VFAltMoveSelectionURI.

The VFAltMoveSelection tag must also include the format parameter to identify a format-file specification which includes the <u>VFSelectTargetObjInput</u> tag. The VFSelectTargetObjInput tag is replaced by HTML INPUT controls (checkboxes) that allow the user to select the new subordinate entries.

The id argument is described under Common arguments.

Chapter 5: Format file

A format file contains Access Presence tags that define the presentation of individual page elements. It defines a finer level of presentation detail than is possible in a page template.

This chapter has the following sections:

- Location and syntax
- Assessment order and examples
- URI and link tags
- Display name tags
- Target object tags
- Alternative hierarchy tags
- <u>Approval process tags</u>

Location and syntax

The format file is identified by the configuration-file parameter <u>webFormatFile</u>. An example is supplied with the demonstration directory, Deltawing: webdir\tmpl\extra.lst.

The format file contains directives in the following form:

```
<format attName objClass formatID optional>
<html to replace the attribute with the attName or objClass goes here
along with the format file tags described in this chapter>
</format>
```

The elements of a directive are described below.

attName

The name of an attribute type, or * to match any attribute type.

When the dnformat argument is declared, the attName should be the attribute holding the entry's DN. (The optional dnformat is an argument for the VFExpandAtt and VFAttVal tags.)

objClass

The name of an attribute type, or * to match any attribute type.

formatID

This is an identifier that corresponds to the value of a tag's format argument.

Many of the template tags have the optional format argument. When declared, the format argument's value will correspond to blocks of format-file entries identified by formatID. The directives within these entries are then applied to the data generated by the tag.

optional

A format directive can include one of the following optional keywords.

Optional keyword	Displays the output defined in the format directive
StartEntry	Before each entry in the search results or in a subordinate list, if it is present.
EndEntry	After each entry in the search results or in a subordinate list, if it is present.
StartFirstEntry	Before the first entry in a search result or subordinate list, if it is present. If not present, StartEntry will be used.
	This keyword applies to the first entry on the page. So for a paged search result, the first entry on each page will be formatted using the StartFirstEntry context.
EndFirstEntry	After the first entry in a search result or subordinate list, if it is present. If not present, EndEntry will be used. This keyword applies to the first entry on the page. So, for a paged search result, the first entry on each page will be formatted using the EndFirstEntry context.
FirstAtt	To the first attribute in each entry.
StartLine	Before the first value of each attribute type.
ClassName	After the output defined in the StartEntry format directive, and before each entry. This keyword is used to generate the display name for subordinate entries displayed by the Expanded Entry page.
StartAtt	Before the first value of a multi-value DN type attribute.
EndAtt	After the last value of a multi-value DN type attribute.
NoAtt	This keyword allows content to be provided for attributes with no value (for example to provide content for a table cell when there is no value to put in it).
RelatedEntryRow	Before each entry displayed by the Search Results page when used in the <u>related-entry workflow</u> .
RelatedEntryEnd	After the last entry displayed by the Search Results page when used in the <u>related-entry workflow</u> .
RequestReason	This keyword relates to the <u>approval process</u> .

Optional keyword	Displays the output defined in the format directive
InputChecked	This keyword relates to the approval process.
FirstValue	To the first value of a multi-valued attribute to be formatted differently to subsequent values.

RequestReason

This keyword identifies directives that define the presentation of the input elements on the Modify page during the approval process.

The directives are invoked as described above – a formatID in the format file corresponds to the format argument of the $\underline{VFModifyAtt}$ tag – but they should also include this keyword.

A directive with the RequestReason keyword must include the VFRequestReason tag, and can also include any of the remaining approval-process tags.

For example:

```
# Request reason input box for modify form.
<format * * reason RequestReason>
  
 Reason for
 submitting update request:
 <VFRequestReason cols="40"
 rows="6">
 <VFRequestSaveInput html='type="submit" value="Submit"
  title="Submit request to modify entry.">'>
  <VFRequestApproveInput html='type="submit" value="Approve"
  title="Approve request to modify entry.">'>
  <VFRequestCancelInput html='type="submit" value="Revoke"</pre>
  title="Revoke request to modify entry.">'>
  <VFRequestRejectInput html='type="submit" value="Reject"
  title="Reject request to modify entry.">'>
 </format>
```

InputChecked

This keyword identifies a set of directives used by the <u>Select Target Object template</u> during the approval process for moving an entry.

The approval process involves the following stages:

1. The user clicks the link to move the current entry in the directory structure. The Select Target Object template is displayed because there are multiple valid new superiors in the target-object cache.

- 2. The user selects one of the valid superiors; and because the approval process is implemented, they also complete the 'request reason' box and submit their request. The request is now pending approval.
- 3. Another user with appropriate access rights logs on (an approver) and views the pending request. As above, it is displayed by the Select Target Object template.

This is the point where InputChecked keyword is used. It defines the presentation so that the template displays the set of valid superiors with the requestor's choice selected. Hence, the approver can then accept or reject the request.

For example:

Assessment order and examples

The order in which format directives are assessed is as follows:

<format< th=""><th>attName</th><th>objClass</th><th>formatID></th><th></th></format<>	attName	objClass	formatID>	
<format< td=""><td>attName</td><td>*</td><td>formatID></td><td></td></format<>	attName	*	formatID>	
<format< td=""><td>*</td><td>objClass</td><td>formatID></td><td></td></format<>	*	objClass	formatID>	
<format< td=""><td>*</td><td>*</td><td>formatID></td><td></td></format<>	*	*	formatID>	
<format< td=""><td>attName</td><td>*</td><td>* ></td><td></td></format<>	attName	*	* >	
<format< td=""><td>*</td><td>objClass</td><td>* ></td><td></td></format<>	*	objClass	* >	
<format< td=""><td>*</td><td>*</td><td>* ></td><td></td></format<>	*	*	* >	

A directive with an optional keyword will, however, take precedence over all the above if it is appropriate.

To illustrate, consider two format directives:

```
<format surName orgPerson Details>
< . . tags . .>
</format>
<format * * Details FirstAtt>
< . . tags . .>
</format>
```

If the first attribute were surName, the second directive would take precedence. Otherwise, it would be ignored and the first directive would be processed.

Example 1

The format directives in this example produce an alternative layout for the Search Results page. Rather than being in a table, entries are list items.

The following screenshot shows the Search Results page containing the results of a search on the surname 'Smith'.



The set of directives is included in the format file (webdir\tmpl\extra.lst) supplied with the demonstration directory, Deltawing, and has been reproduced below. For the sake of the example, each directive has been numbered.

```
<format * * searchR StartEntry>
                                 - 1
 <1i>
</format>
<format * * searchR EndEntry> - 2
 </format>
<format * * searchR FirstAtt>
                               - 3
 <VFHref><VFAttVal></A>
</format>
<format location * searchR>
                             - 4
 which is located at <VFAttVal>
</format>
<format organizationalUnitName organizationalUnit searchR FirstAtt>
                                                                     - 5
 Unit <VFHref><VFAttVal></A>
</format>
<format hierarchyName organizationalPerson searchR>
                                                     - 6
 works in <VFAttVal>
</format>
<format organizationalUnitName organizationalUnit searchR>
                                                            - 7
 Unit <VFAttVal>
</format>
```

```
<format telephoneNumber organizationalPerson searchR> - 8
and can be contracted by phoning <VFAttVal>
</format>
<format telephoneNumber organizationalUnit searchR> - 9
has a common telephone number: <VFAttVal>
</format>
<format * * searchR> - 10
<VFAttVal>
</format>
```

For the results shown in the above screenshot, the directives are processed as follows (the numbers on the left correspond to those in the above example):

- 1. The HTML tag is generated.
- 3. The Access Presence tag <VFHref> is replaced with the entry's first attribute and linked to the entry's Expanded Entry page. The <VFAttVal> tag is replaced by the next attribute value in the entry, first name.
- 6. The text 'works in' is displayed followed by the next attribute value.
- 4. The text 'which is located at' is displayed followed by the next attribute value.
- 8. The text 'and can be contacted by phoning' is displayed followed by the next attribute value.
- 2. The HTML tag is generated.

Example 2

This example comprises two format file directives:

```
<format manager * parentEntry>
  <VFAttVal id=manager DNFormat=nameAndTitle>
  </format>
  <format * * nameAndTitle>
    <div class="entryName"><VFHRef><VFAttVal id=commonName></a></div>
  </format>
```

The first directive relates to the attribute manager, and tells Access Presence to apply the <u>VFAttVal</u> tag to the attribute. The tag's DNFormat argument invokes the second directive, which tells Access Presence to display the manager's <code>commonName</code> as a hypertext link to their entry. (The DNFormat argument is only relevant to DN type attributes.)

URI and link tags

These tags relate to URIs and links, and are primarily intended for use in the format file, but may also be used in the Access Presence templates.

<VFURI [id=*CHAR] [scope= {base | entry | *CHAR}]>

This tag is replaced by the URI for the current entry. The id and scope arguments are described under Common tags and arguments.

<VFHref [id=*CHAR] [html=1*CHAR]>

This tag is replaced by a hypertext link to the Expanded Entry page displaying the current entry.

The id argument can be used to create a hypertext link to an extra <u>Expanded Entry</u> <u>template</u>. Set this argument to '_default' to cause the standard Expanded Entry template to be used.

The html argument is described under Common tags and arguments.

<VFAddValueHref [id=*CHAR] [html=1*CHAR]>

This tag is replaced by a hypertext link to the Modify Value Form for adding a new value to a multi-value attribute, if the current user has permission to add values of the attribute.

The id and html arguments are described under Common tags and arguments.

NOTE: This tag can only be used to generate links on the Expanded Entry page.

<VFModifyValueHref [id=*CHAR] [html=1*CHAR]>

This tag is replaced by a hypertext link to the Modify Value Form for modifying or removing and existing value of a multi-value attribute, if the current user has permission to modify or remove values of the attribute.

The id and html arguments are described under Common tags and arguments.

NOTE: This tag can only be used to generate links on the Expanded Entry page.

<VFOrderHref action={ top | bottom |up | down } [id=*CHAR] [html=1*CHAR]>

This tag is replaced by a hypertext link that allows a user to change the position of the selected entry within its list of sibling entries of the same structural object class.

The action attribute has one of the following values:

- top moves the entry to the top of the group
- bottom moves the entry to the bottom of the group
- up moves the entry up one position in the group
- down moves the entry down one position in the group

The id and html arguments are described under Common tags and arguments.

NOTE: This tag can also appear in an Expanded Entry template.

<VFOrderResetHref html=*CHAR>

This tag is replaced by a hypertext link that allows a user to move the selected entry to its default position within its set of sibling entries of the same structural object class. The default location is based on the alphabetical order of the entry's first attribute.

The ability to move entries is provided to users by implementing the <u>VFOrderHref</u> tag.

NOTE: This tag can also appear in an Expanded Entry template.

<VFRandomNum>

This tag causes Access Presence to generate a random number. It is used to generate a value for the id attribute of an HTML tag.

<vFOEL [style=crlf]>

This tag is replaced by an end-of-line character sequence. The character sequence generated is platform dependent – for example, on Unix LF and on Windows CRLF.

When the style argument is set to crlf, the tag generates the CRLF sequence as the end-of-line character sequence.

Display name tags

Object classes and attributes have display names (and optional icons) which are displayed by Access Presence.

An attribute has a default display name. It can also have a different display name (and icon) to be displayed when the attribute is associated with a specific object class.

For example, consider an attribute called name, which is used by two object classes: country and device. The display name for the attribute when it is used by the country object class might be 'Country Name'; and the display name when it is used by the device object class might be 'Device Name'. Access Presence displays the appropriate display name for the attribute.

An attribute display name (and icon) is defined through either:

- ViewDS Management Agent see help topic View or modify an attribute's DUA presentation.
- Stream DUA see the display-name component of the operational attribute attributePresentation.

An object class display name is declared through either:

- ViewDS Management Agent see help topic View or modify an object class's DUA presentation.
- Stream DUA see the displayName component of the operational attribute objectClassPresentation.

The following tags can also appear in any Access Presence template.

```
<VFAttVal id=1*CHAR [escval=on|off] [list=1*DIGIT] [width=1*DIGIT
[preChar=CHAR] [postChar=CHAR]] [scope= {base | user | *CHAR}]
[unqualified] [DNFormat=1*CHAR] [delimiter=1*CHAR]
[valueformat=1*CHAR] [[reference=1*CHAR] | [path=1*CHAR]] >
```

This tag is replaced by the set of values for the attribute named by the id argument. The values are for the attribute in the currently displayed entry.

escval

When the escval argument is on, the value generated by this tag is 'escaped' to make it safe for use as a URI.

list

This argument can be used to reference a specific value in a multi-valued attribute. The first value is identified by a 1: List=1

Access Presence ignores this argument if it is set to zero, a negative number, or a nonnumeric character.

When list is absent, all values are displayed, separated by the delimiter defined for in the attribute's DUA presentation. See the ViewDS Management Agent help topic *View or modify an attribute's DUA presentation*, or attributePresentation.

width

Specifies the maximum field width for attribute values. If an attribute value is longer than the width, it is truncated and appended with the characters `..'.

preChar postChar

preChar specifies a padding character to precede values shorter than the field width set by the width argument.

postChar specifies a padding character to append values with a length shorter than that set by the width argument.

When neither preChar nor postChar are defined, postChar defaults to a space character. When both are defined, short values are centred in the field width defined by width.

scope

This argument is described under <u>Common tags and arguments</u>.

unqualified

Affects the behaviour of Access Presence when a user searches on a component of an attribute with a complex syntax (such as certificates and XML documents). If the argument is declared, Access Presence replaces the tag with all component values; otherwise, Access Presence replaces the tag with just the component value the user searched on.

dnFormat

References a format file directive that defines how a DN type attribute is displayed. It allows more than just the name of an entry to be displayed to the user – see Example 2.

delimiter

Identifies a delimiter character that overrides the default set for an attribute (see the ViewDS Management Agent help topic *View or modify an attribute's DUA presentation*).

For example: <VFAttVal id='businessCategory' delimiter=';'>

valueformat

Identifies the format file specification for the individual values of a multi-valued attribute. The referenced format file specification is restricted to the following tags and arguments (all of which are described in detail elsewhere in this guide):

- VFAttName all supported arguments allowed
- VFAttIcon all supported arguments allowed
- VFAttType all supported arguments allowed
- VFAttVal escval, width, preChar, postChar, dnformat, reference or path
- VFQueryURI id, escval, raw, scope

The referenced format specification can also include optional <u>format directives</u>. For example, the directive <code>FirstValue</code> allows the first value of a multi-valued attribute to be formatted differently to subsequent values.

reference

Specifies an ASN.1 component reference to identify a simple component of a complex ASN.1 type to be displayed. The simple components supported are Booleans, integers, strings, object identifiers, date-time fields and distinguished names. This argument only applies when the VFAttVal tag is used to format individual values of a multi-valued attribute. Only one out of reference and path may be included. If the reference argument is present then any path argument will be ignored.

path

Specifies an XML component path to identify a simple component of a complex XML type to be displayed. The simple components supported are Booleans, integers, strings, object identifiers, date-time fields and distinguished names. The argument only applies when the VFAttVal tag is used to format individual values of a multi-valued attribute. Only one out of reference and path may be included. If the reference argument is present then any path argument will be ignored.

<VFAttName id=1*CHAR [ifChanged] [force] [scope={ base | user | *CHAR}]>

This tag is replaced by the display name for the attribute named by the id argument.

ifChanged

If this argument is declared, the display name is only displayed if it has changed since the tag was last invoked.

force

This argument overrides the behaviour of the 'show icons only' option presented in the search options on the Search Form. This can be useful for the search result headings.

scope

This argument is described under <u>Common tags and arguments</u>.

<VFAttIcon id=1*CHAR [scope={ base | user | *CHAR}]>

This tag is replaced by the icon associated with the attribute named by the id argument. The icon must be a .gif file stored in the ../icons directory.

The scope argument is described under Common tags and arguments.

<VFAttType id=1*CHAR [scope={ base | user | *CHAR}]>

This tag is replaced by the type of the attribute named by the id argument.

The scope argument is described under Common tags and arguments.

<VFClassName [ifChanged]>

This tag is replaced by the display name of the object class of the current entry. This can be the entry in the Expanded Entry page or the subentry in a list of subordinate entries.

If the *ifChanged* argument is declared, the display name is only displayed if it has changed since the tag was last invoked.

<VFAttSize id=1*CHAR [scope= {base | user | *CHAR}] [unqualified] [label=*CHAR] [modifier=1*DIGIT]>

This tag is replaced by the number of values in a multi-valued attribute named by the id argument.

scope

This argument is described under Common tags and arguments.

unqualified

Affects the behaviour of Access Presence when a user searches on a component of an attribute with a complex syntax (such as certificates and XML documents). If the argument is declared, Access Presence replaces the tag with all component values; otherwise, Access Presence replaces the tag with just the component value the user searched on.

label

Allows a label to be set to prefix the number of attribute values. The label is only displayed if the number of values in the attribute is greater than 1.

This argument provides support for the HTML <code>rowspan</code> and <code>colspan</code> properties in the HTML table row and cell elements. For example, <tr<VFAttSize label="
rowspan">> results in for a single-value attribute, and for an attribute with two values.

modifier

A signed integer modifier that is applied to the number of attribute values. Useful, for example, to generate meaningful 'rowcount' values.

Target object tags

These tags relate to the target object (see page $\underline{1}$) and can appear in either a target object template (see page $\underline{1}$) or format file.

<VFAddTargetObjHref [confirm] [html=1*CHAR [id=*CHAR]>

This tag is replaced by a link that adds the current entry to the target-object cache. Access Presence, however, will only generate the link if the entry is not in the target-object cache.

The confirm, html and id arguments are described under <u>Common tags and</u> arguments.

<VFDeleteTargetObjHref [confirm] [html=1*CHAR [id=*CHAR]>

This tag is replaced by a link that removes the current entry from the target-object cache. Access Presence, however, will only generate the link if the entry is not in the target-object cache.

The confirm, html and id arguments are described under Common tags and arguments.

<VFSelectTargetObjInput>

This tag generates HTML INPUT controls, each with a NAME and VALUE. The INPUT controls must be submitted in a FORM that uses the POST method and whose ACTION is the URL generated by the VFShowTargetObjectsURI tag:

<form method="post" action="<VFShowTargetObjectsURI>">

Each <u>target object template</u> includes a tag which identifies a format-file specification containing the VFSelectTargetObjInput tag. The result is that INPUT controls are displayed that allow the user to select a target object in the cache. The behaviour when the form is submitted differs according to each template.

Any parameters for the VFSelectTargetObjInput tag (aside from NAME and VALUE) should be declared, including a TYPE parameter to ensure the correct type of element is generated. For example:

<VFSelectTargetObjInput type="checkbox">

The TYPE should be 'checkbox' for pages that allow multiple items to be selected, and 'radio' for pages that allow only a single item to be selected.

The VFSelectTargetObjInput tag can also appear in a format-file specification referenced by several other template tags: VFExpandDn, VFExpandSubclass, VFExpandAltSubord and VFSearchResults. This allows entries in a subordinate listing or search result – which have been selected by the user – to be added to the target-object cache.

Alternative hierarchy tags

These tags relate to the <u>target object</u> and can be used in a format file to list subordinate entries or search results:

- <u>VFAltRemoveHref</u>
- VFAltExpandHref
- <u>VFLabel</u>

The VFAltType tag described below can also be used in a format file or template.

```
<VFAltType [type=AttributeName] [force] [scope={ base | user | *CHAR}]>
```

This tag can be used in a format file and the following templates:

- Select Entries to Add to Alternative Hierarchy template
- Select Entries to Move in Alternative Hierarchy template

It generates the label for the alternative hierarchy identified by the <u>VFExpandAltSubord</u> tag's type parameter. This can be overridden by the type attribute of the VFAltType.

The force argument overrides the behaviour of the 'show icons only' option presented in the search options on the Search Form. This can be useful for the search result headings.

The scope argument is described under Common tags and arguments.

Approval process tags

The tags in this subsection can be used in templates and format files.

They can be used in the format file to define an alternative presentation of the input elements displayed on the Modify page during the <u>approval process</u>. The tags should appear in a format-file directive that includes the optional keyword <u>RequestReason</u>. The directive can then be invoked by the format argument of the <u>VFModifyAtt</u> tag.

These tags are also used in the <u>Request Remove Entry template</u>.

<VFRequestReason [rows=1*DIGIT] [cols==1*DIGIT]</pre>

This tag is replaced by an HTML INPUT text box that allows the user to enter a comment when submitting or modifying an update request.

The tag can be included in a format file entry, which has the keyword RequestReason, in order to change the appearance of the input box. (Note that Access Presence automatically adds a default input box to the pages that allow an update request to be submitted or modified.)

The ${\tt rows}$ and ${\tt cols}$ arguments set the dimensions of the text box.

<VFRequestSaveInput [html=1*CHAR] >

This tag is replaced by an HTML INPUT element (by default, a submit button) that allows the user to **submit** an update request.

The tag can be included in a format file entry, which has the keyword RequestReason, in order to change the appearance of the input element. (Note that Access Presence automatically adds a default submit button to a page that allows a request to be submitted.)

The default value of the <u>html</u> argument is as follows:

'value="Submit" title="Submit" type="submit">'

The HTML INPUT element is only generated if the user has permission to submit the update request.

<VFRequestCancelInput [html=1*CHAR]>

This tag is replaced by an HTML INPUT element (by default, a SUBMIT button) that allows the user to cancel an update request.

The tag can be included in a format file entry, which has the keyword RequestReason, in order to change the appearance of the input element. (Note that Access Presence automatically adds a default button to a page that allows a request to be cancelled.)

The default value of the html argument is as follows:

'value="Revoke" title="Revoke" type="submit">'

The HTML INPUT element is only generated if the user has permission to cancel the update request.

<VFRequestApproveInput [html=1*CHAR]>

This tag is replaced by an HTML INPUT element (by default, a SUBMIT button) that allows the user to **approve** an update request.

The tag can be included in a format file entry, which has the keyword RequestReason, in order to change the appearance of the input element. (Note that Access Presence automatically adds a default button to a page that allows a request to be approved.)

The default value of the <u>html</u> argument is as follows:

'value="Approve" title="Approve" type="submit">'

The HTML INPUT element is only generated if the user has permission to approve the update request.

<VFRequestRejectInput [html=1*CHAR]>

This tag is replaced by an HTML INPUT element (by default, a SUBMIT button) that allows the user to **reject** an update request.

The tag can be included in a format file entry, which has the keyword RequestReason, in order to change the appearance of the input element. (Note that Access Presence automatically adds a default button to a page that allows a request to be rejected.)

The default value of the <u>html</u> argument is as follows:

'value="Reject" title="Reject" type="submit">'

The HTML INPUT element is only generated if the user has permission to reject the update request.

Chapter 6: Server-side attributes

This chapter describes the attributes stored by the Directory System Agent (DSA) that control different aspects of Access Presence. For example, there are presentation operational attributes that specify how a particular class of entry is displayed by Access Presence.

This chapter has the following sections:

- <u>Concepts</u>
- DUA presentation operational attributes
- User operational attributes
- <u>Approval process operation attributes</u>
- New entry operation attributes
- Other operational attributes

Any DUA can use the attributes described in this chapter. Access Presence uses all the attributes unless otherwise stated in an individual attribute description.

Important note

The operational attributes described in this chapter can be managed using the Stream DUA (see *ViewDS Directory Server: Technical Reference Guide*).

Alternatively, you can manage the same attributes through the ViewDS Management Agent. The application has a help system that includes an overview of the concepts and functionality described in this chapter.

NOTE: See the help topic *Key concepts for DUA presentation*.

Concepts

When a DUA starts up, it binds to the DSA and obtains user-specific operational attributes. The DUA then determines the base entry, which allows it to obtain schema and presentation operational attributes.

Each of these steps is described below.

Obtain user-specific operational attributes

After binding to a DSA, the DUA obtains user-specific operational attributes from the user's entry in the Directory Information Tree (DIT).

The attributes are:

- userEntitlement
- userConfig
- privilege

These attributes are normally changed automatically by a running DUA, or by an administrator performing administration functions with an interactive DUA. The Stream DUA is not normally used with these attributes.

Obtain a base entry

The DUA attempts to obtain the Distinguished Name (DN) of a base entry from one of the following in the order shown:

- the user-specific operational attribute, userConfig
- the subschema administrative point that governs the user's entry
- the configuration-file parameter <code>baseentry</code> (when Access Presence and the DSA are on different hosts, each has its own configuration file; when located on the same host, Access Presence and the DSA share the same configuration file)

Obtain operational attributes

The DUA obtains schema and presentation operational attributes from the base entry. They provide the DUA with its understanding of the DSA's schema, and configure its start-up banners and messages, the layout of the Search and Expanded Entry page, operational limits, and other features.

Schema operational attributes

The DUA obtains the following schema operational attributes (described in the *ViewDS Directory Server: Technical Reference Guide*):

- attributeTypes
- objectClasses
- matchingRuleUse
- nameForms
- dITStructureRules
- dITContentRules
- definitions

They define the schema from the base entry, and are usually declared as part of configuring schema rather than the DUA.

DUA presentation operational attributes

These attributes define the appearance of different aspects of the DUA. They can be modified using the Stream DUA, or the ViewDS Management Agent, and must be in a subschema subentry. For information about the Stream DUA, see the *ViewDS Directory Server: Technical Reference Guide*.

The DUA presentation operational attributes are described in the following subsection.

DUA presentation operational attributes

These attributes are single-valued, except for attributePresentation and objectClassPresentation which are multi-valued:

- duaBanners
- attributePresentation
- objectClassPresentation
- searchOptions
- defaultEntitlement

duaBanners

The duaBanners operational attribute specifies:

- information displayed by the DUA at logon (or soon after)
- the banner for the Search Form
- an optional set of key mappings to override the built-in mappings (deprecated)

It is defined as follows:

```
duaBanners ATTRIBUTE ::= {
 WITH SYNTAXDUABanners
 SINGLE VALUETRUE
 USAGEdirectoryOperation
 ID{vf 18 4}
}
DUABanners ::= SEQUENCE {
 start-banner1[0]TeletexString OPTIONAL,
 start-banner2[1]TeletexString OPTIONAL,
 startup-message[2]SEQUENCE OF TeletexString OPTIONAL,
 search-banner[3]TeletexString OPTIONAL,
 vt100-key-overrides[4]KeyMappings OPTIONAL,
 pc-key-overrides[5]KeyMappings OPTIONAL
}
KeyMappings ::= SEQUENCE OF KeyMapping-- DEPRECATED
KeyMapping ::= SEQUENCE {-- DEPRECATED
 action[0]DUAAction,
  keys[1]SEQUENCE OF Key
```

```
DUAAction ::= ENUMERATED { startfield, endfield, -- etc -- refresh }
Key ::= ENUMERATED { kb-a, kb-b, -- etc -- alt-fn12 }
```

Components

}

start-banner1

Specifies a string displayed on the first line of the Search Form page of Access Presence.

For example:

start-banner1 "DELTAWING CORPORATE DIRECTORY"

start-banners

Deprecated.

startup-message

Specifies a string displayed on the first line of the Welcome page of Access Presence.

search-banner

Specifies a string displayed at the top of the Search Results page of Access Presence.

For example:

search-banner "DELTAWING CORPORATE DIRECTORY"

Examples

The following Stream DUA script reads the duaBanners attribute. Because DUA presentation attributes are available throughout a subschema area, the attributes can be read from the Deltawing entry itself.

```
read
organizationName "Deltawing"
return duaBanners;
```

The following script sets duaBanners. As the DUA presentation attributes can only be modified at the subentry where they are held, the modify operation must be directed to the subschema subentry.

```
modify
organizationName "Deltawing"
/ commonName "Subschema"
with changes {
  remove attribute duaBanners,
  add attribute duaBanners {
    start-banner1 "DELTAWING CORPORATE DIRECTORY",
    start-banner2 "On-line Edition",
    startup-message {
```

```
"Caution!!", "System going down at 3.30. p.m."
},
search-banner "DELTAWING CORPORATE DIRECTORY"
};
```

attributePresentation

The multi-valued attributePresentation attribute specifies how attributes are displayed in the Search, Expanded Entry and Modify Value Form pages. It has the following ASN.1 definition:

```
attributePresentation ATTRIBUTE ::= {
               AttributePresentation
 WITH SYNTAX
 EQUALITY MATCHING RULE objectIdentifierFirstComponentMatch
 USAGE
                     directoryOperation
ID
                      {vf 18 5}
}
AttributePresentation ::= SEQUENCE {
 type [0] ATTRIBUTE.&id,
display-names [1] SEQUENCE OF DisplayName,
         [2] AttributeFlags OPTIONAL,
 flags
 delimiters [3] TeletexString DEFAULT ";",
 preprocessing [4] SEQUENCE OF PrepFunction OPTIONAL,
 attrib-hiding [5] SEQUENCE OF AttribHiding OPTIONAL,
 replace-strings [6] ReplaceStrings OPTIONAL,
 description [7] UnboundedDirectoryString OPTIONAL,
 dateTimeFormat [8] UTF8String OPTIONAL,
          [9] AttributeFields OPTIONAL
 fields
)
DisplayName ::= SEQUENCE {
 name TeletexString,
 classes SEQUENCE OF OBJECT-CLASS.&id OPTIONAL
}
AttributeFlags ::= BIT STRING {
 fixedWidth (0), -- Not Used
 globallyChangeable (1),
 matchingValuesOnly (2),
 approximateMatch (3), -- Not Used
 formattedText
                  (4),
 isEmailAddress
                 (5),
 isURL
                  (6),
 isHTML
                  (7),
isBinary
                  (8),
 sortDNValues (9)
}
```

```
AttribHiding ::= SEQUENCE {
 object-class OBJECT-CLASS.&id,
 privileges SET OF AccessLevel
}
AccesLevel ::= ENUMERATED {
 none (0),
 read
         (1),
update
          (2),
 admin (3),
 superuser (4)
}
ReplaceStrings ::= SEQUENCE OF ReplaceString
ReplaceString ::= SEQUENCE {
 replace (0) TeletexString ,
 with (1) TeletexString
}
AttributeFields ::= SEQUENCE OF AttributeField
AttributeField ::= SEQUENCE {
 name (0) UTF8String , -- field name in syntax
          (1) UTF8String , -- display name for field
 label
 behaviour AttributeFieldBehaviour DEFAULT normal:NULL
}
AttributeFieldBehaviour ::= CHOICE {
 normal (2) NULL,
 formatted (3) NULL ,
 constrained (4) SEQUENCE of UTF8String ,
 uuid (5) NULL,
 uri
           (6) NULL
}
```

For the ASN.1 definition of PrepFunction (see Preprocessing functions).

Components

type

type specifies the attribute to which the value of attributePresentation applies. It is either a symbolic name or object identifier. For example:

```
type surname
type {2 5 4 4}
```

display-names

display-names specifies a sequence of display name records. Each consists of:

- a string which is the display name of the attribute; and
- a sequence of structural object classes to which display name applies.

When the attribute is displayed in the Expanded Entry page, the DUA displays the name that corresponds to the structural object class of the entry.

The first display-name record should have an omitted or empty sequence of object class. It is the default name used – for example, on the Search Form or for a structural object class that is not listed explicitly. Usually, this default name is sufficient and further display-name records are unnecessary.

The structural object classes can be specified by name or object identifier.

A display-name string can be appended with a '%' character followed by an integer. The integer identifies an icon displayed next to (or instead of) the display name. The icons and their numbers are shown below.

Icon No	Icon	Application
10	œ	Locality
20	٥	Generic non-leaf entry
21	G	Org unit entry
22	8	Org unit entry
23	<i>.</i> %.	(No suggested application)
24	Ø	(No suggested application)
30	0	Generic leaf entry
31	Ħ	Person entry
32	G	Person entry
33	G 2	Group
40	a <u>n</u>	Telephone no.
41	Ŧ	Telephone no.
50	æ	Facsimile no.
51	2	Device entry
60	2	Postal address
61	E	Email address
62	82	X.400 address

Icon No	Icon	Application
70	≣≣	Description
71	2	Description
80	\$	Role / See also
81	ন্দ্র	Role / See also
82	<u>ê</u> ,	Note
90		Note
91	Å	Note

For example:

```
display-names {
  {name "Telephone%41"},
  {name "Enquiries%41", classes {organizationalUnit}},
  {name "Phone%41", classes {conferenceRoom}} }
```

In this example:

- for object class <code>organizationalUnit</code>, the display name of the attribute type is <code>Enquiries</code>
- for object class conferenceRoom, the display name of the attribute type is Phone
- for all other object classes, the display name of the attribute type is Telephone

In all cases, the DUA displays icon 41 next to the attribute.

flags

Specifies a set of flags for an attribute type. For example: flags {isEmailAddress}

globallyChangeable

The attribute is available for global changes (see Global changes templates).

matchingValuesOnly

If the attribute has multiple values, this flag specifies that the Search Results page will only list the value that matches the search criteria.

formattedText

Specifies that the DUA should display the attribute's value in a text box. A user can enter a value with simple text formatting (line-breaks and tabs), which the DUA will retain.

isEmailAddress

Specifies that the attribute's value should be displayed as an email address. For example,
with the value name@host, the DUA would display: name@host

isURL

Specifies that the attribute's value is a URL (Universal Reference Locator; see RFC 1738). For example, with the value http://www.deltawing.com.au, the DUA would display: www.deltawing.com.au

isHTML

Specifies that the attribute's value is a HTML text. For example, with the following value:

```
Press <a href=telnet://www.deltawing.com.au /> here</a> to access
www.deltawing.com.au
```

The DUA would display:

Press here to access www.deltawing.com.au

WARNING: Using this flag leaves Access Presence vulnerable to cross-site scripting attacks.

isBinary

Specifies that the attribute's value is a binary and that Access Presence should not display it, but allow it to be downloaded.

sortDNValues

For an attribute that has multiple DN values, this flag specifies that Access Presence should sort the values alphabetically on the Expanded Entry page.

delimiters

Specifies the set of delimiter characters for the attribute type. It specifies the valid characters that can be used to separate values of the attribute type within a single string. It defaults to a semicolon, and usually does not need to be specified.

Of special interest is the delimiter cr (which must be specified using the compound string format in Stream DUA). This delimiter is the best choice for attributes which may contain semicolons, such as orAddress. Also, if the first delimiter character is cr, the DUA displays the attribute with each value on a new line.

Examples:

delimiters {";", cr}

This specifies that values of the attribute entered by the user must be separated by either semicolons or new-lines; and that when multiple values are displayed, they are separated by new-lines.

preprocessing

Specifies a list of preprocessing functions for an attribute type. The DUA applies the preprocessing functions whenever the user modifies a value of the attribute.

It only applies to attributes with a string syntax, and is ignored for all others. Structured attributes (such as orAddress or telexNumber) are represented as strings in the DUAs,

but are stored in the DSA in a structured form. Conversion to and from the structured form may result in changes to the value entered by the user, but this is not preprocessing.

The component is a sequence of preprocessing function arguments, each argument is labelled by the function name. Two names are defined for each function, one beginning with 'm' for mandatory, the other with 'op' for optional. Optional functions are ignored if the user has turned off preprocessing. For example:

preprocessing {mCompress : NULL, opUniqueValues : NULL}

Note that the ordering of the list is significant as it is the order in which the preprocessing functions are executed. Executing a list of functions in one order may not have the same effect as executing them in another.

The functions are described under <u>Preprocessing functions</u>.

attrib-hiding

Deprecated.

replace-strings

Deprecated.

description

Describes how the attribute should be used and is displayed on Modify page.

dateTimeFormat

Defines the date/time presentation of an attribute that has a GeneralizedTime or UTCTime syntax.

The format string can include the following specifiers (plus arbitrary text):

- %% replaced with a literal '%' character
- %C century number [0,99], two characters padded by zero
- %d day of month [1,31], two characters padded by zero
- %D−%m/%d/%y
- %F−%Y-%m-%d
- %H hour (24-hour clock) [0,23], two characters padded by zero
- %j day number of year [1,366], three characters padded by zero
- %m month [1,12], two characters padded by 0
- %M minute [0,59], two characters padded by 0
- %**R−%H:%M**
- %s fraction of second
- %S seconds [0,60], two characters padded by zero
- %T−%H:%M:%S
- gy year without century [0,99], two characters padded by zero
- %Y year with century

- % z time zone as hour/minute offset from UTC, four characters padded by zero preceded by '+' or '-' sign or 'Z' for UTC
- %Z time zone as hour/minute offset from UTC in XML format, '+' or '-' followed by 2 digits for hour, a colon ':' and the 2 digits for minutes

Examples

The following Stream DUA script reads all values of attributePresentation:

```
read {
    organizationName "Deltawing" }
return { attributePresentation };
```

The following script adds an attributePresentation value for the attribute surname:

```
modify {
    organizationName "Deltawing"
    / commonName "Subschema"
}
with changes {
    add values attributePresentation {
    type surname,
    display-names {{name "Surname"}},
    flags {},
    preprocessing {opCompress},
    attrib-hiding {},
    replace-strings {}
  };
```

fields

Controls the presentation of the component fields of a complex attribute value. This information is used primarily on the Modify Value Form, although some fields also affect the Expanded Entry page.

name	The name of the field in the syntax definition.
label	The display name to use for the field on the Modify Value Form.
behaviour	Provides information about how field values should be presented, as described below:
normal	The default presentation for the syntax - a text input control.
formatted	A textarea input control.
constrained	Allows a list of permitted values for the field to be provided. These will be presented in a select input control.
uuid	Indicates that the field holds a value that should be treated as a string representation of the entryUUID attribute value of an entry in the directory. Access Presence will

display such fields in the way it does for a <code>DistinguishedName</code>, using the entry cache to provide candidate values on the Modify Value Form.

uri Indicates that the field holds a URI that should be presented as a link on the Expanded Entry page.

objectClassPresentation

This multi-valued operational attribute specifies how directory entries are displayed in the Expanded Entry page of Access Presence.

It has the following ASN.1 definition:

```
objectClassPresentation ATTRIBUTE ::= {
 WITH SYNTAX
                       ObjectClassPresentation
 EQUALITY MATCHING RULE objectIdentifierFirstComponentMatch
 USAGE
                       directoryOperation
 ID
                       {vf 18 6}
}
ObjectClassPresentation ::= SEQUENCE {
 object-class [0] OBJECT-CLASS.&id,
 displayName
                   [1] TeletexString,
 sub-classes
                  [2] SEQUENCE OF Subord OPTIONAL,
 expanded-atts
                  [3] SEQUENCE OF ATTRIBUTE.&id,
 special-att
                  [4] AttNumb OPTIONAL,
    -- number is column position --
 modify-atts [5] SEQUENCE OF ATTRIBUTE.&id,
 inherit-atts
                   [6] SEQUENCE OF ATTRIBUTE.&id OPTIONAL,
 username-atts
                  [7] SEQUENCE OF AttNumb OPTIONAL,
    -- number is #chars to use (0 is all) --
 exp-name-label [8] TeletexString OPTIONAL,
 rdn-atts
                   [24] SEQUENCE OF ATTRIBUTE.&id OPTIONAL,
 mand-atts
                   [25] SEQUENCE OF ATTRIBUTE.&id OPTIONAL,
                  [26] SEQUENCE OF ATTRIBUTE.&id OPTIONAL,
 opt-atts
 useNamingOptionals [9] BOOLEAN DEFAULT FALSE,
 reverseLink [10] SEQUENCE OF ReverseLink OPTIONAL,
 relatedEntries
                  [11] RelatedEntries OPTIONAL,
                  [12] ATTRIBUTE.&id OPTIONAL,
 preferredName
 request-atts
                  [13] SEQUENCE OF ATTRIBUTE.&id OPTIONAL
}
ReverseLink ::= SEQUENCE {
 forwardType ATTRIBUTE.&id,
 reverse SEQUENCE OF ReverseLinkItem
ReverseLinkItem ::= %M:SetReverseLinkItem SEQUENCE {
                             ATTRIBUTE.&id,
 type
 objectClass
                             OBJECT-CLASS.&id OPTIONAL,
 exclude
                             ReverseLinkOperation OPTIONAL,
```

```
deleteValuesReferencingMoved BOOLEAN DEFAULT FALSE
}
ReverseLinkOperation ::= BIT STRING {
 add
       (0),
 remove (1),
 modify (2),
 rename (3),
 move (4)
}
Subord ::= SEQUENCE {
 -- subClasses has replaced subClass, which exists for
 -- compatability with old versions
 -- If both are present, subClass is ignored
 subClass OBJECT-CLASS.&id OPTIONAL,
 subClasses SEQUENCE OF OBJECT-CLASS.&id OPTIONAL,
 subClassName TeletexString,
 attributeInfo SEQUENCE OF AttNumb
 -- number is width as percentage --
}
AttNumb ::= SEQUENCE {
 type ATTRIBUTE.&id,
number INTEGER
}
RelatedEntries ::= SEQUENCE {
 alternativeClass [0] OBJECT-CLASS.&id,
 linkAttribute [1] ATTRIBUTE.&id,
 searchForm
                 [2] TeletexString
}
```

Components

object-class

Specifies the object class to which the value of <code>objectClassPresentation</code> applies. It is either a symbolic name or object identifier.

For example:

```
object-class organizationalUnit
object-class {1 3 32 0 2 4 6 0}
```

displayName

Specifies a single display name for the object class. It is the name displayed to the user instead of the object class's actual name. For example, the display name for the organizationalPerson class might be 'Staff member'.

The display name is used by the DUA when a user adds a new subordinate entry, or moves or deletes an existing entry. As with an attribute, the display name for an object class can be appended with a '%' character followed by an integer to associate it with an icon (see <u>display-names</u>).

For example: display-name "Unit"

sub-classes

Specifies information about groups of classes subordinate to the object class. The subordinates within each group are sorted and displayed together.

The information about each group of subordinate classes consists of object identifiers, display names when displayed as subordinates, and the attribute types and their position for display.

NOTE: The number attached to the attribute type is its display width (as a percentage of the total available display width). A width of zero can be specified for an attribute type so that the attribute is not displayed, but is used when sorting results.

The subordinate classes listed must be consistent with the permitted subordinate classes defined by the structure rules in the schema attribute dITStructureRules (see the *ViewDS Directory Server: Technical Reference Guide*). However, a subordinate class specified in dITStructureRules can be omitted from this component.

For example:

```
sub-classes {
  {
    subClasses organizationalPerson, organizationalRole,
    subClassName "Staff & Roles",
    attributeInfo {
        {type commonName, number 45},
        {type role, number 33},
        {type telephoneNumber, number 25}
    }
}
```

This example specifies two subordinate classes for the object class whose objectClassPresentation is being defined (assumed to be organizationalUnit): organizationalPerson and organizationalRole. The attributes displayed are common to both classes.

expanded-atts

Specifies the attributes displayed on the Expanded Entry page for entries of the object class. The order in which the attributes are listed determines the order in which they are displayed by the DUA. For example: expanded-atts {telephoneNo, location}

special-att

Specifies an attribute, such as telephoneNumber, to be displayed at the top of the Expanded Entry page and to the right of the entry name.

The column number has been deprecated.

For example: special-att {type telephoneNumber, number 45}

modify-atts

Specifies attribute types to be presented for users to modify when adding or modifying an entry. The order in which the attributes are listed determines the order in which they are displayed by the DUA.

This component should be consistent with the mandatory and optional attributes specified through the schema attributes objectClasses and dITContentRules (see the *ViewDS Directory Server: Technical Reference Guide*). The DUA appends omitted mandatory attributes, and omits specified attributes that are neither mandatory nor optional.

For example:

```
modify-atts {
    organizationalUnitName,
    location,
    telephoneNumber,
    keylink
}
```

inherit-atts

Specifies attributes to be inherited from an entry's immediate superior when an entry of this object class is created (added).

For example: inherit-atts {location}

username-atts

Specifies the attribute types and numbers used to construct the user name for entries of this object class. The numbers define the number of characters to use from a value of the specified attribute type (a value of 0 means use the entire attribute value).

The attribute types specified must be mandatory for the object class. That is, they must be specified as mandatory in the <code>objectClasses</code> (or <code>dITContentRules</code>) schema attributes (see the *ViewDS Directory Server: Technical Reference Guide*).

For example:

```
username-atts {
  {type givenName, number 1},
  {type surname, number 6}
}
```

This example builds user names by concatenating the first character of the attribute givenName with the first six characters of the attribute surname.

exp-name-label

Specifies a label for entries of this object class. It is shown next to the entry name in the Expanded Entry page.

For example: exp-name-label "NAME: "

useNamingOptionals

Specifies a Boolean flag to indicate whether optional naming attributes should be used to form an entry's DN when values of the optional naming attributes are provided on the Modify page. (Optional naming attributes are identified in the name form for the structural object class of the entry.)

For example: userNamingOptionals TRUE

reverseLink

Specifies rules for automatically maintaining DN references between entries. When an entry is referenced by a second entry using a DN value, reverseLinks can be used to automatically include a reverse reference from the first entry to the second. The reverseLinks rules define when this should happen and what attributes should be used for the reverse link.

The forwardType field identifies which attribute type (in the object class the objectClassPresentation applies to) should trigger a reverse link in the referenced entry.

The reverse field is a list of rules identifying the attribute type (in the referenced entry) to which the DN of the referencing entry should be added. An element in the list with an <code>objectClass</code> field will identify the behaviour to use when the referenced entry is of the identified object class. An element in the list without an <code>objectClass</code> field identifies the default behaviour.

The exclude field identifies operation types for which the reverse-link value should not be maintained. The deleteValuesReferencingMoved field, when set to TRUE, indicates that if the referenced entry is moved to a new superior, both the forward and reverse links should be removed. For example:

```
reverseLink {
    {
      forwardType roleOccupant,
      reverse {
        type seeAlso,
        deleteValuesReferencingMoved TRUE
     }
    }
}
```


This example defines that when a roleOccupant of an organizationalRole entry refers to another entry, to identify the occupant of the role, the referenced entry will have a seeAlso attribute value added to it identifying the organizationalRole referencing it. If the entry referenced by the roleOccupant value is moved to another superior, the roleOccupant value and the seeAlso value referencing the organizationalRole entry will be removed.

NOTE: The reverse links and DN tracking functionality overlap considerably (see *dnTracking* in the *Indexes, extensions and word lists* chapter of the *ViewDS Directory Server: Technical Reference Guide*). If configured inconsistently they can behave unpredictably.

RelatedEntries

RelatedEntries works in conjunction with reverseLink to provide a workflow for Access Presence users when they add multiple entries for the same person. The workflow encourages the user to create roles for a person who already has an entry.

To illustrate, related entries ensure that a person with multiple entries has one main entry of a particular class (organizationalPerson, for example) and several related entries of an alternative class (organizationalRole, for example). An example is shown in the following illustration.



When a user adds a new entry for the above <code>organizationalPerson</code>, the workflow is as follows.

- 1. Access Presence presents the user with a Search Form (the type of Search Form is identified by the searchForm field of RelatedEntries).
- 2. The user searches for 'John Self'.
- 3. The Search Results page lists all entries that fit the search criteria, and displays a button next to each that allows the user to create a new organizationalRole. The page also gives the user the option to create a new organizationalPerson entry.
- 4. The user creates a new organizationalRole for an entry. Access Presence automatically populates the new entry's attributes with the user's search criteria (so they don't have to enter the same information twice).
- 5. Access Presence adds a related-entry link to the new organizationalRole entry, to all existing organizationalRole entries, and to the organizationalPerson entry.

RelatedEntries has the following fields:

- alternativeClass the object identifier of the object class to use for the subsequent entries for an entity (for example, OrganizationalRole).
- linkAttribute when present, identifies an attribute with DistinguishedName syntax in the object class identified by the alternativeClass field. This enables the link back to the original entry for example, roleOccupant referring back to the OrganizationalPerson entry.
- searchForm the name of the Search Form used to determine whether an entity
 already exists (this should match a forms.type field in the searchOptions attribute).
 The Search Form should restrict matching object classes, using the filter-for field to
 specify a single-occurrence object class (for example, OrganizationalPerson).

preferredName

A preferred name attribute can be defined for a class of entry. The value of the attribute is then used as an entry's label in the Access Presence pages, providing an alternative to using the default label. The default is the entry's mandatory naming attribute defined by schema.

The value of a preferred name attribute also appears in the labels generated by the <u>VFLabel</u> tag and for links to Distinguished Names. The preferred name can be accessed through either the Stream DUA or through the ViewDS Management Agent – see the help topic *View or modify an object class's DUA presentation*.

request-atts

This field identifies the attributes that can be accessed by a 'requestor' in the <u>approval</u> <u>process</u>.

Examples

The following script reads all values of the <code>objectClassPresentation</code> attribute:

```
read { organizationName "Deltawing" }
```

```
return { objectClassPresentation };
```

The following Stream DUA script adds an <code>objectClassPresentation</code> value for the object class <code>organizationalUnit</code>:

```
modify {
 organizationName "Deltawing"
 / commonName "Subschema"
}
with changes {
 add values objectClassPresentation {
  class organizationalUnit,
   displayName "Unit",
   sub-classes {
    {
       subClass organizationalPerson,
       subClassName "Staff",
       attributeInfo {
          {type commonName, number 45},
          {type title, number 30},
          {type telephoneNumber, number 25}
       }
    }
    {
      subClass organizationalUnit,
       subClassName "Unit",
    attributeInfo {}
    }
   },
   expanded-atts { manager, postalAddress, function },
   modify-atts { manager, postalAddress, chargeCode, function }
  }
};
```

This sets the display name for the object class to Unit and defines how the two subclasses organizationalPerson and organizationalUnit should be displayed. It declares three attributes to be displayed when the entry is expanded, and four attributes to be displayed for modification.

searchOptions

This single-valued operational attribute specifies the characteristics of the Search Forms, along with other miscellaneous details.

```
searchOptions ATTRIBUTE ::= {
  WITH SYNTAX SearchOptions
```

```
SINGLE VALUE TRUE
 USAGE
             directoryOperation
 ΙD
             {vf 18 7}
}
SearchOptions ::= SEQUENCE {
             [0] SEQUENCE OF SearchForm,
 forms
 context-atts [1] SEQUENCE OF ATTRIBUTE.&id,
 abbrev-atts [2] SEQUENCE OF AttribPair OPTIONAL,
    -- first is abbrev of second --
             [3] BIT STRING {
 flags
                             (0),
                 autoExpand
                  topDownSuperiors (1),
                  complexSearching (2) } OPTIONAL,
 pseudo-rdn-level [4] INTEGER DEFAULT 1,
 max-att-label-len [5] INTEGER DEFAULT 11
}
SearchForm ::= SEQUENCE {
                          [0] UnboundedDirectoryString,
 tvpe
 filter-for
                          [1] SEQUENCE OF OBJECT-CLASS.&id OPTIONAL,
 base-object
                          [2] DistinguishedName OPTIONAL,
                          [3] SEQUENCE OF AttField,
 row1-atts
                          [4] SEQUENCE OF AttField OPTIONAL,
 row2-atts
 row3-atts
                          [5] SEQUENCE OF AttField OPTIONAL,
                          [6] SEQUENCE OF SortKey,
 srch-sort-atts
 hierarchyNameBehaviour [7] HierarchyNameBehaviour DEFAULT
 abbreviated,
                    [8] OrderingStrategy OPTIONAL,
 orderingStrategy
 orderEmptyFieldsAsGreater [9] BOOLEAN DEFAULT FALSE
}
OrderingStrategy ::= ENUMERATED {
 sortKeys
                      (0),
 searchFields
                      (1),
 firstValueExactMatch (2),
 anyValueExactMatch (3)
}
AttField ::= %M:SetAttField SEQUENCE {
 type ATTRIBUTE.&id,
          INTEGER,
 number
          BOOLEAN DEFAULT TRUE,
 dnAtt
 component ComponentField OPTIONAL,
 name UTF8String OPTIONAL,
 location [0] AttFieldLocation Default both
}
ComponentField ::= SEQUENCE {
 identifier ComponentKind,
  rule MATCHING-RULE.&id
```

```
}
ComponentKind ::= CHOICE {
 reference [0] ComponentReference,
 path [1] ComponentPath
}
HierarchyNameBehaviour ::= ENUMERATED {
               (0),
 none
abbreviated (1),
 unabbreviated (2)
}
AttFieldLocation ::= ENUMERATED {
 request (1),
 result (2),
 both (3)
}
```

SearchOptions

forms

Specifies the characteristics for a DUA Search Form.

context-atts

Specifies the attribute types that can hold a context. A context is a set of default values entered into the Search Form whenever the user clears the form 'to the context' – for example, a telephone-number prefix. The component is a sequence of attribute types. For example:

```
context-atts {
   organizationalUnitName,
   location,
   telephoneNumber
}
```

abbrev-atts

Specifies abbreviated attributes to be used in search requests. It is a sequence of attribute pairs: the first attribute in a pair is the abbreviated equivalent of the second.

If an attribute type is specified for a Search Form and is also specified by this component as having an abbreviated equivalent, the abbreviated equivalent attribute type (and value) is requested in a search instead of the full attribute type.

The abbreviated attributes can be generated by the DSA (for example hierarchyName) but can be any alternative attribute. For instance, you might choose to display a user's initials in place of their given name to save space on the Search Results page.

flagspseudo-rdn-levelmax-att-label-len

Deprecated.

SearchForm

type

The name of the form – typical values are Name search, Function search, and Unit search. It allows arbitrary search forms, including ones with base objects in other DSAs and other schema administrative areas.

filter-for

A list of object classes to include in the search filter constructed from the form. For example, for the Unit search form, it should list the object classes considered to be units.

base-object

The base object for the search. If absent, the base object is the same as the configurationfile parameter base-entry.

row1-atts

The list of attributes, their column positions (as a percentage of total available width) running across the first row of search fields on the form, and a dnAtt Boolean. Only row1-atts are displayed in the Search Results page (although Access Presence allows the user to alter this).

The dnAtt Boolean indicates whether the attributes in the DN of entries should be searched as well as the attributes in the entries themselves. If it is set to false then DN will not be searched. This is appropriate if the structure rules allow the attribute type to be present in the DN of entries belonging to the object classes to be searched and such occurrences are to be excluded from the search evaluation.

If multiple attributes are given at the same column in the same row, the attribute is overloaded. This means:

- There is one input field for the set of overloaded attributes.
- A search will try to match values for all the overloaded attributes. For example, if attributes telephoneNumber and extensionNumber are overloaded, and the user enters a value 3456 on the search form, the DUA will construct a filter telephoneNumber=3456 or extensionNumber=3456.
- All the overloaded attributes are requested to be returned from a DSA search.
- The attribute type (out of the set of overloaded attribute types) to be displayed in the search results is the first one for which a value has been returned when scanning through the list of overloaded attribute types in a particular order. This is the order specified by the disp-pref component of the userConfig attribute in the user's entry (if any) followed by the order of occurrence of the overloaded attributes in the Search Form Attributes.

row2-atts

The list of attributes and their column positions for the form's second row of search fields.

row3-atts

The list of attributes and their column positions for the form's third row of search fields.

srch-sort-atts

A list of the attribute types that defines the sort order for search results. The search results are first sorted by object class to ensure that all entries of the same object class are displayed together. Next, entries of the same object class are sorted on the first attribute type in srch-sort-atts. If there are values of the first attribute type that are the same, then values of the second attribute type in srch-sort-atts are compared, and so on. Note that when comparing attribute values, all the values that exactly match the value entered into the corresponding input field are sorted ahead of all other values. The values that do not match the value entered into the input field are sorted lexicographically, and follow the exact matches.

For example:

```
forms {
    {
        type "Name search",
        filter-for {},
        row1-atts {
            {type surname, number 0},
            {type givenName, number 20},
            {type organizationalUnitName, number 40},
            {type location, number 60},
            {type telephoneNumber, number 80},
            {type extensionNumber, number 80}
        },
        srch-sort-atts { surname, givenName }
}
```

hierarchyNameBehaviour

This field is used to control how <code>organizationalUnitName</code> values are displayed on the Search Results page. By default, the <code>organizationalUnitName</code> attribute is displayed as a pair of abbreviated values derived from the DN of the displayed entry.

The hierarchyNameBehaviour field can be used to alter this default behaviour. When set to none, the organizationalUnitName behaves like any other attribute: the only organizationalUnitName attribute values displayed are those actually defined in the current entry (that is, the DN is ignored). When set to unabbreviated, the organizationalUnitName is displayed using the same values from the DN as are used in the default behaviour except these values will not be abbreviated.

For example: hierarchyNameBehaviour none

orderingStrategy

This field identifies the search ordering strategy for the Search Results page. (To set the results ordering for a Search Form through the ViewDS Management Agent, see the help topic *View or modify a Search Form*.)

orderEmptyFieldsAsGreater

Whether Access Presence sorts empty values to the bottom (TRUE) or to the top (FALSE) of the Search Results page.

AttField

The AttField type is referenced by the row1-atts, row2-atts and row3-atts fields in the SearchForm type. It allows components of complex syntaxes to be identified as separate fields that can be searched individually from a Search Form page. (For information about complex syntaxes, see attributeSyntax in the Schema chapter of the ViewDS Directory Server: Technical Reference Guide.) The referenced component should be a syntax supported for searching – that is, a string, time or integer type.

The name in AttField allows the name of a search field to be specified. This name is the label displayed to the user, and overrides the attribute display name.

The location in AttField defines whether a search field is displayed on the Search Form page, Search Results page, or both (the default).

defaultEntitlement

This single-valued operational attribute specifies limits and functional capabilities for a user. Access Presence enforces these limits (however, other DUAs may not observe them).

This attribute should be placed in the subschema subentry. It provides a system-wide limit for all users. However, it can be overridden for a specific user by placing the userEntitlement attribute (which has the same syntax) in the user's entry.

This attribute has the following ASN.1 definition:

```
defaultEntitlement ATTRIBUTE ::= {
 WITH SYNTAX UserEntitlement
 SINGLE VALUE TRUE
 USAGE directoryOperation
 ID
             {vf 18 12}
}
UserEntitlement ::= SEQUENCE {
 limit [1] Limit OPTIONAL,
 func-cap [2] FunctionalCapabilities OPTIONAL,
 gc-limit [3] Limit OPTIONAL
 -- for global changes: timeout is actually subsearch limit --
}
Limit ::= SEQUENCE {
 time-limit [0] INTEGER,
 size-limit [1] INTEGER,
 timeout [2] INTEGER
}
FunctionalCapabilities ::= BIT STRING {
 globalChanges
                (0),
```

```
sortSubs (1),
moveMultipleSubs (2),
viewUsers (3),
printing (4),
statistics (5),
billing (6),
viewLogs (7),
allowSavePassword (8)
}
```

Components

limit

Specifies several time and size limits, and is a sequence of three integers:

- time-limit is the time limit in seconds to request for each DSA operation. A typical value is 30 seconds.
- size-limit is the size limit (number of entries to return) to request for a search-one-level operation (i.e. listing immediate subordinates).
- timeout is the maximum inactive time in seconds, after which the DUA will disconnect from the DSA. A typical value is 1800 seconds (30 minutes).

If this component is absent (and is not supplied by a value of <code>userEntitlement</code> in the user's entry), the DUA does not set any limits never times out.

For example:

limit { time-limit 30, size-limit 99, timeout 1800 }

func-cap

Specifies functional capabilities available to a user with update or administrator access. (Super-users have implicit access to all functional capabilities provided by the DUA.)

The following functional capabilities can be specified:

Identifier	Description
globalChanges	Allows the user to modify all entries within their assigned subtree that satisfy certain selection criteria with a single command.
sortSubs	Allows the user to change the sort order of subordinates on an expanded entry form (for example, by selecting them and moving them to the top of the list of entries for that subordinate class).
moveMultipleSubs	Allows the user to select multiple subordinate entries on an expanded entry form and then move them to another entry.
viewUsers	Deprecated.
printing	Allows the user to invoke the Printed Reports command of Access Presence.
statistics	Deprecated.

Identifier	Description
billing	
viewLogs	
allowSavePassword	

For example:

func-cap {globalChanges, sortSubs, printing}

gc-limit (not supported by Access Presence)

Specifies time and size limits for the global-changes facility. The global-changes facility allows a user to apply a single command to modify all entries in a specific subtree that satisfy their selection criteria.

To do this efficiently, and to handle when the number of entries exceeds the system limits (set by the parameters sizelimit and timelimit), the DUA uses a special method of searching for the entries to be modified. It attempts a full subtree search on the base entry. If this search results in a size limit or time limit problem, the search is broken into a listing of immediate subordinates followed by a full subtree search on each subordinate. If these subordinate searches fail with a size limit or time limit, they are handled in the same way, recursively.

For best performance the size limit and time limit requested by the DSA for the full subtree searches may need to be greater than the normal limits for searching. The gc-limit component allows suitably relaxed limits to be specified. It is a sequence of three integers:

- time-limit is the time limit in seconds to use for global changes searches (typically, 75 seconds).
- size-limit is the size limit to use for global changes searches (typically, 500).
- timeout is not a timeout at all, but is the size limit to use for global changes subordinate searches (typically, 10000).

If this component is absent (and is not supplied by a value of <code>userEntitlement</code> in the user's entry), the DUA does not set any limits in its global changes operation requests, and the DSA's <code>sizelimit</code> and <code>timelimit</code> apply. The DSA's limits also apply if the specified limits exceed the DSA's.

For example:

```
gc-limit { time-limit 75, size-limit 500, timeout 10000 }
```

Examples

The following Stream DUA script reads the defaultEntitlement attribute:

```
read { organizationName "Deltawing" }
return { defaultEntitlement };
```

The following script modifies an existing value of defaultEntitlement by removing the old value and adding a new value:

```
modify {
    organizationName "Deltawing"
    / commonName "Subschema"
}
with changes {
    remove attribute defaultEntitlement,
    add defaultEntitlement {
    limit { time-limit 30, size-limit 100, timeout 1800 },
    func-cap {globalChanges, sortSubs, printing},
    gc-limit { time-limit 75, size-limit 500, timeout 10000 }}
};
```

This sets the system-wide parameters and functional capabilities to the values specified.

Preprocessing functions

The preprocessing functions can only be applied to attributes that have a string syntax (for example, TeletexString, DirectoryString). A preprocessing function is ignored if it is not specified according to the descriptions in this subsection.

A preprocessing function is described by its ASN.1 tag (which translates to a choice of value) and its value (which supplies an argument to the function).

```
PrepFunction ::= CHOICE {
 opCompress [0] NULL,
             [1] NULL,
[2] TeletexString,
mCompress
 opCompare
mCompare
               [3] TeletexString,
               [4] TeletexString,
 opRemove
 mRemove
               [5] TeletexString,
               [6] TeletexString,
 opReplace
 mReplace
               [7] TeletexString,
 opCase
               [8] TeletexString,
 mCase
               [9] TeletexString,
 opReplaceWords [10] ReplaceStrings,
 mReplaceWords [11] ReplaceStrings,
 opCompareWords [12] ReplaceStrings,
 mCompareWords [13] ReplaceStrings,
 opLength
               [14] TeletexString,
 mLength
               [15] TeletexString,
 opTruncate
               [16] INTEGER,
 mTruncate [17] INTEGER,
 opUniqueValues [22] NULL,
 mUniqueValues [23] NULL,
```

```
opPhone
                  [24] TeletexString,
 mPhone
                 [25] TeletexString,
 opCommonName
                 [26] AttribPair,
 mCommonName [27] AttribPair,
 opBuildAttribute [28] AttribBuildSpec,
 mBuildAttribute [29] AttribBuildSpec,
 opBuildAbbrev [30] AttribAbbrevSpec,
 mBuildAbbrev
                 [31] AttribAbbrevSpec,
 opRegexpMatch
                 [32] UTF8String,
 mRegexpMatch
                [33] UTF8String
}
AttribPair ::= SEQUENCE {
 attrib1 ATTRIBUTE.&id,
 attrib2 ATTRIBUTE.&id
}
AttribBuildSpec ::= SEQUENCE {
 string TeletexString,
 attributes SEQUENCE OF ATTRIBUTE.&id
}
AttribAbbrevSpec ::= SEQUENCE {
 abbrevAtt [0] ATTRIBUTE.&id,
 sourceAtt [1] ATTRIBUTE.&id,
 delimiter [2] TeletexString OPTIONAL
}
```

Each function is available as a mandatory function (starts with an 'm') or optional function (starts with 'op'). When an Access Presence user enters a string value, they have the option to switch off preprocessing. However, switching off a mandatory function has no effect and it is still applied.

Two additional preprocessing functions are applied implicitly when attribute information is modified. If the attribute is single valued, the DUA checks whether the user entered multiple values, and reports an error if so. (To disable this, explicitly define the delimiters for the attribute to be an empty string.) If the attribute is multi-valued, the DUA checks that the values are all different and removes duplicates if necessary.

Compress

This preprocessing function removes leading and trailing spaces, multiple spaces between words, and unprintable characters (except for carriage return) from an attribute's value. For example: opCompress: NULL

Compare chars

This preprocessing function compares all characters in an attribute's value against a set of specified characters. It reports an error if any characters in the value are not in the set.

It consists of one of the characters A, N, L, D, or U, which specifies a basic character set. Optionally, this is followed by either an I or E, to include or exclude a subsequent set of characters.

- A All characters
- N No characters
- L Alpha characters only
- D Digits only
- U Alpha-numeric characters only
- Istring The attribute's value must include any of the characters in string

Estring The attribute's value must not include any of the characters in string

For example, to report an error if punctuation is entered for a new or changed attribute value, specify: mCompare: "AE.,:;"

Remove chars

This preprocessing function compares all characters in an attribute's value against a set of specified characters. It removes any characters from the value that are not in the set.

The supplied value specifies the set of permitted characters, which is defined in the same way as for the Compare chars function.

For example, to remove punctuation from value, specify: opRemove: "AE., :;"

Replace chars

This preprocessing function replaces certain characters in an attribute's value with other characters.

The supplied value specifies the substitutions. It has the form: RcharsWchars

The characters following the R specify the characters to be replaced; the characters following the W are the replacements.

For example, to replace all space characters with underscores and all # characters with \$ characters, specify: opReplace: "R #W_\$"

Case

This preprocessing function converts the characters in an attribute value to upper, lower, or mixed case.

The conversion algorithm for mixed case makes some assumptions about the usage of certain punctuation characters – for example, an apostrophe is assumed to be used as in the example, D'Rosario. There is no special recognition of certain standard naming prefixes such as 'Mac'. Therefore, a name such as 'MacKenzie' would be converted to 'Mackenzie'. These sorts of problems in the mixed case conversions mean that it is preferable to only offer this preprocessing function in an optional application. It can then be overridden by a DUA user.

The supplied value specifies the type of conversion:

- U Convert to upper case
- L Convert to lower case
- M Convert to mixed case (the first letter of each word in upper case; and other letters in lower case)

For example, to convert an attribute value to mixed case: opCase: "M"

Replace words

This preprocessing function replaces certain words in an attribute value. Words that appear in the replacement list are replaced by a replacement word. For example, to convert addresses to a standard abbreviated form:

```
opReplaceWords: {
   { replace "Road", with "Rd." },
   { replace "Street", with "St." },
   { replace "Avenue", with "Ave." }
}
```

Compare words

This preprocessing function compares the words in an attribute value with a replacement list. It reports an error if there is a word in the attribute value that is not in the list.

The with words should be empty strings. For example, to restrict values of an attribute to either Dr, Mr, Mrs, Ms, or Miss:

```
opCompareWords: {
    { replace "Dr", with "" },
    { replace "Mr", with "" },
    { replace "Mrs", with "" },
    { replace "Ms", with "" },
    { replace "Miss", with "" }
}
```

Access Presence displays the compare words for an attribute as permitted values in a list box. Additional constraints apply to the attribute if specified in the attributeSyntax field of the attributeType operational attribute (see attributeSyntax in the Schema chapter of the ViewDS Directory Server: Technical Reference Guide.).

Length

This preprocessing function checks whether the length of an attribute value is within specified bounds, and reports an error if it is not.

The supplied value specifies the bounds:

Lnum	$length \le num$
Gnum	length \geq num

Lnum GZnum	length \leq num length > num or length = 0
Lnum1Gnum2 Or Gnum2Lnum1	length \leq num ₁ and length \geq num ₂
Lnum1GZnum2 or GZnum2Lnum1	length \leq num ₁ and length \geq num ₂ or length = 0

For example, to specify that attribute values are to be either five or six characters long: opLength: "G5L6"

To specify an exact length, use LnumGnum with both num terms set to the exact length.

Truncate

This preprocessing function truncates an attribute value to the length specified by the supplied value (an integer). For example, to specify that an attribute value is to be truncated to eight characters: opTruncate: 8

Unique values

This preprocessing function checks that the values in a string are unique within an area of the DIT on the local DSA. If they are not unique, the function reports an error.

NOTE: As applying this function involves a search of the directory, the attribute must be indexed.

For example: opUniqueValues: NULL

Phone

This preprocessing function checks whether an attribute value has one of the specified telephone number syntaxes. If the value conforms to one of the syntaxes, the function preprocesses the value to a standard format (also specified by the syntax it matches). If it does not conform, the function reports an error.

Each specified syntax defines an acceptable pattern of numbers. It is a string containing one of more patterns, separated by semi-colons. When more than one pattern is specified, strings are compared for matches from left to right and the first match is selected for preprocessing.

A telephone number syntax can contain the following characters:

d	Pattern matches a digit (0-9) – for example, (dd) ddd dddd
a	Pattern matches an alphanumeric character – for example, ddd-aaa
0123456789	Any digit may be placed in specific position in the string and an entered value must match exactly – for example, 13 dd dd
[]	Pattern matches any single character within [] – for example, 041[789] ddd ddd
() + - space	Need not be present but would be inserted if not present and removed if not appropriate.

Note that leading and trailing spaces in the string are inserted into the formatted telephone number.

In the special case where two consecutive format strings are equal (when ignoring the formatting characters () + – *space*) then the positions of any spaces will determine the matching format which will be used for preprocessing. That is, the format string that matches the most consecutive spaces from the beginning will be selected.

For example:

mPhone: "13 dd dd;(dd) ddd dddd;(ddd) ddd ddd"

With this example:

- 07 2584505 would be formatted to (07) 258 4505;
- 072 584505 would be formatted to (072) 584 505; and
- 072584505 would be formatted to (07) 258 4505 because of the ordering of the format string.

Common name

This preprocessing function checks whether a value contains the values of two other attributes, and reports an error if it does not. It should be specified as one of the preprocessing functions for the commonName attribute to ensure that its value contains the surname and one of the givenName attribute values of the entry.

For example:

opCommonName: { attrib1 givenName, attrib2 surname }

Build attribute

This preprocessing function builds attribute values from a combination of other attribute values or constant text. Its main purpose is to allow the <code>commonName</code> attribute value to be modified automatically whenever one of the <code>personalTitle</code>, <code>givenName</code>, or <code>surname</code> attribute values are modified.

The supplied value consists of a TeletexString and a list of attributes, and specifies how the first attribute in the attribute list is built. The string can include the following:

- % the built attribute is formed by replacing each % character with the next attribute in the attributes list
- \sim an escape character that allows a literal % or \sim to be included in the built attribute
- constant text

For example:

```
opBuildAttribute: {
  string "% % %",
  attributes { commonName, personalTitle, givenName, surname } }
```

Abbreviate attribute

This preprocessing function builds an attribute value by abbreviating other attribute values (it takes the first letter from each). A common use of this function is to automatically update an initials attribute when a value of the givenName attribute is created or modified.

The supplied value consists of two attributes and a delimiter:

- abbrevAtt names the abbreviated attribute to be generated or maintained
- sourceAtt names the attribute which supplies the non-abbreviated value
- delimiter is typically a '.' or ''

The abbrevAtt attribute is formed by dividing the value of sourceAtt into words separated by spaces, taking the first letter of each word, and concatenating them with the delimiter (if present) between each letter and after the last.

This preprocessing function should be specified for <code>sourceAtt</code>.

For example:

```
opAbbrevAtt: {
   abbrevAtt initials,
   sourceAtt givenName,
delimiter '.' }
```

Regular expression match

This preprocessing function verifies an attribute's value according to whether it matches a provided regular expression (that conforms to the XPath specification).

The regular expression is not anchored. The '^' and '\$' characters are the start and end anchors respectively.

User operational attributes

Access Presence reads attributes from a user's entry, which affect Access Presence's operation for that user. They are:

- userEntitlement
- userConfig
- privilege

The above attributes are described in this section, except for privilege which is described in the Managing Security chapter of the *ViewDS Directory Server: Technical Reference Guide*.

userEntitlement

This single-valued operational attribute specifies limits and functional capabilities assigned to a particular user. Access Presence enforces these limits (other DUAs may not).

To apply this attribute's limits to a user, place it in the user's entry. If a user's entry does not have this attribute, the system-wide limit defined by defaultEntitlement in the

subschema subentry applies. The attribute has the following ASN.1 definition (for the attribute's syntax, see <u>defaultEntitlement</u>):

```
userEntitlement ATTRIBUTE ::= {
  WITH SYNTAX UserEntitlement
  SINGLE VALUE TRUE
  USAGE directoryOperation
  ID {vf 18 8}
}
```

For example, the following Stream DUA script reads the userEntitlement attribute for the entry organizationName "Deltawing" / commonName "John Smith":

```
read {
   organizationName "Deltawing"
   / commonName "John Smith" }
   return { userEntitlement };
```

The following script modifies an existing value of userEntitlement by removing the old value and adding a new value:

```
modify {
   organizationName "Deltawing"
   / commonName "John Smith" }
with changes {
   add userEntitlement {
    limit { time-limit 30, size-limit 100, timeout 1800 },
    func-cap {globalChanges, sortSubs, printing},
    gc-limit { time-limit 75, size-limit 500, timeout 10000 }
   }
};
```

This sets the user's parameters and functional capabilities to the values specified.

NOTE: The values of userEntitlement can also be added to user entries by a user with admin or superuser privilege using Access Presence.

userConfig

This operational attribute records the user's preferred settings for several user-specific options in Access Presence.

```
userConfig ATTRIBUTE ::= {
  WITH SYNTAX UserConfig
  SINGLE VALUE TRUE
  USAGE directoryOperation
```

```
ΙD
              {vf 18 9}
}
UserConfig ::= SEQUENCE {
 context [0] SEQUENCE OF AttString OPTIONAL },
 default-base [1] DistinguishedName OPTIONAL
 disp-pref [2] SEQUENCE OF ATTRIBUTE.&id OPTIONAL,
 language
             [3] Language OPTIONAL,
 codepage
             [4] CodePage OPTIONAL
     DEPRECATED
}
AttString ::= SEQUENCE {
 attribute ATTRIBUTE.&id,
 valueString TeletexString
}
```

context

Specifies the user's context at DUA startup. It is a list of attribute types with string values. If these attribute types are in a Search Form, and the context is enabled, then the string values are displayed in the appropriate fields so that the user does not have to enter them.

For example:

context {{attribute telephoneNumber, value "(03) 9876"}}

default-base

Specifies a base object to use in directory searches in preference to the base-entry specified in the configuration file. If used, it typically specifies a sub-unit below the base entry.

For example:

```
default-base { organizationName "Deltawing" / organizationalUnit "R&D
Labs"}
```

disp-pref

Not supported by Access Presence.

Specifies the user's display preferences on a search form when attributes are overloaded and values of more than one of the overloaded attributes are available.

For example, if telephoneNumber and extensionNumber are overloaded, and a value is available for both, then the DUA must decide which value to show. It chooses the first attribute in the disp-pref sequence of attribute types. It must be set using the Stream DUA.

For example:

disp-pref {extensionNumber, telephoneNumber}

Approval process operation attributes

The operation attributes for the approval process are described below.

```
viewDSUpdateRequest ATTRIBUTE ::= {
 WITH SYNTAX UpdateRequest
 EQUALITY MATCHING RULE directoryStringFirstComponentMatch
 USAGE directoryOperation
 ID id-viewDS-oa-updateRequest
}
UpdateRequest ::= SEQUENCE {
 identifier [0] UnboundedDirectoryString,
 -- Recommended that this is a UUID in string representation
 activity [1] SEQUENCE SIZE (1..MAX) OF UpdateActivity,
 -- Every request should include a creation activity record
 details
            [2] UpdateRequestDetails,
          [3] DistinguishedName OPTIONAL
 object
  -- Object name only required when: the request is not stored in the
 entry it applies to; and it is not an add subordinate request.
}
UpdateActivity ::= SEQUENCE {
 action [0] UpdateAction,
 name
             [1] DistinguishedName,
 at.
             [2] GeneralizedTime,
 description [3] UTF8String OPTIONAL
}
UpdateAction ::= ENUMERATED {
           (0),
 created
 updated
              (1),
             (2),
 approved
 rejected
              (3),
 cancelled
             (4),
 notification (5)
}
UpdateRequestDetails ::= CHOICE {
 add [0] SEQUENCE {
  structural [1] OBJECT-CLASS.&id,
   nameform [2] NAME-FORM.&id OPTIONAL,
            [3] SET OF Attribute
   content
   -- The distinguished values will be determined from the entry content
   and schema when the request is approved.
   -- The parent is determined by the entry the request is stored in.
 },
 remove [1] NULL,
 move [2] DistinguishedName, -- of the new superior
 modify [3] SET OF Attribute
}
```

The set of attributes for the modify request lists all the attributes modified in the request and the resulting set of values for each attribute. This will include attributes with no values, indicating that the attribute was removed.

New entry operation attributes

These operational attributes relate to when a user creates a new entry:

- newSubordinateModifyRights
- permittedNewSubordinates
- permittedImports

newSubordinateModifyRights

Access Presence uses this attribute when a user adds a new entry. It ensures that the user is presented with only the attributes they are permitted to access according to the access-control scheme.

```
newSubordinateModifyRights ATTRIBUTE ::= {
 WITH SYNTAX NewSubordinateModifyRights
 SINGLE VALUE
                     TRUE
 NO USER MODIFICATION TRUE
 USAGE
                     directoryOperation
 ΙD
                      id-adacel-oa-newSubordinateModifyRights
}
SubordinateModifyRights ::= %M:SetSubordinateModifyRights SEQUENCE {
 structural OBJECT-CLASS.&id,
 auxiliaries SET OF OBJECT-CLASS.&id,
 modifyRights ModifyRights
}
NewSubordinateModifyRights ::= SEQUENCE OF SubordinateModifyRights
```

A SubordinateModifyRights element is created for each combination of auxiliary object class values that are permitted by the schema and the access controls.

When a user attempts to add a new subordinate entry, then the parent entry's newSubordinateModifyRights is obtained. This describes the modify rights for a subordinate entry, which allows Access Presence to display an Add page that takes the appropriate access controls into account.

It also allows Access Presence to populate the objectClass attribute of a new entry with suggested auxiliary object class values. However, this only occurs if the newSubordinateModifyRights indicates that adding the structural object class without values of an auxiliary object class is not permitted.

permittedNewSubordinates

For each entry, this attribute lists the name forms for entries that can be created as subordinates to the entry. If the access controls permit no subordinates, an empty list is

provided. If the DSA cannot determine a suitable list, the attribute is not returned.

```
PermittedNewSubordinates ::= SEQUENCE OF NAME-FORM.&id
permittedNewSubordinates ATTRIBUTE ::= {
  WITH SYNTAX PermittedNewSubordinates
  SINGLE VALUE TRUE
  NO USER MODIFICATION TRUE
  USAGE directoryOperation
  ID id-adacel-oa-permittedNewSubordinates
}
```

permittedImports

For each entry, this attribute lists the name forms for existing entries that the user can move within the DIT to become subordinate to the entry. If the access controls permit no subordinates, an empty list is provided. If the DSA cannot determine a suitable list, the attribute is not returned.

```
PermittedImports ::= SEQUENCE OF NAME-FORM.&id
permittedImports ATTRIBUTE ::= {
  WITH SYNTAX PermittedImports
  SINGLE VALUE TRUE
  NO USER MODIFICATION TRUE
  USAGE directoryOperation
  ID id-adacel-oa-permittedImports
}
```

Other operational attributes

ViewDS has a number of ViewDS-specific user and operational attributes which are used by Access Presence in special ways:

- sortSubs
- hierarchyName
- unabbreviatedHierarchyName
- updatersName
- viewDSMatchQuality and viewDSSimpleMatchQuality
- viewDSSessionObject

Finally, the following operational attributes are not used directly by Access Presence, but are used by the DSA to generate information used by Access Presence:

- hierarchyNameSpecification
- resolvedDistinguishedName

sortSubs

sortSubs is a simple text string used by Access Presence as a sort-key when listing

subordinates of a given object class. It allows designated people or units to appear ahead of their natural sort position (typically alphabetical-by-name).

It is a user attribute that must be defined in the schema to appear in entries. The DUA will request the attribute if it is defined in the schema.

It should not normally be included in <code>attributePresentation</code>.

```
sortSubs ATTRIBUTE ::= {
  WITH SYNTAX PrintableString
  EQUALITY MATCHING RULE caseExactMatch
  ORDERING MATCHING RULE caseExactOrderingMatch
  SUBSTRINGS MATCHING RULE caseExactSubstringsMatch
  SINGLE VALUE TRUE
  ID {vf 4 0}
}
```

hierarchyName

This operational attribute is a text string that holds an abbreviated representation of an entry's superior units.

The DSA constructs the value from the entry's DN, and according to the specification in the hierarchyNameSpecification attribute that is in the subschema administrative area containing the entry.

The hierarchyName attribute is displayed on a Search Form wherever the forms component defines that an organizationalUnitName attribute should be displayed. If the entry can have subordinates, the DUA replaces the second component with the RDN of the entry itself. Both RDNs are abbreviated.

```
hierarchyName ATTRIBUTE ::= {
  SUBTYPE OF name
  WITH SYNTAX DirectoryString { ub-name }
  SINGLE VALUE TRUE
  NO USER MODIFICATION TRUE
  ID {vf 4 1}
}
```

hierarchyNameSpecification

This operational attribute can be used to control the components of a DN which construct the attributes hierarchyName and unabbreviatedHierarchyName. The hierarchyNameSpecification should be defined in a subschema subentry.

```
hierarchyNameSpecification ATTRIBUTE ::= {
WITH SYNTAX HierarchyNameSpecification
EQUALITY MATCHING RULE objectIdentifierFirstComponentMatch
USAGE dSAOperation
```

```
ΙD
                      { ads 18 2 }
}
HierarchyNameSpecification ::= SEQUENCE {
 structuralObjectClass OBJECT-CLASS.&id,
 delimiter
                     DirectoryString{ub-name}
                   DEFAULT UTF8String:";",
                   HierarchyNameSelection OPTIONAL,
 topBound [0]
 bottomBound [1]
                     HierarchyNameSelection OPTIONAL,
                      SEQUENCE OF HierarchyNameComponent
 specification
}
HierarchyNameComponent ::= SEQUENCE {
 selection HierarchyNameSelection,
 preferredAVA SEQUENCE OF ATTRIBUTE.&id OPTIONAL
HierarchyNameSelection ::= CHOICE {
 top [0] INTEGER,
 autonomous [1] INTEGER,
 bottom [2] INTEGER
}
```

The hierarchyNameSpecification is a multi-valued attribute, where each value defines the rules for building hierarchyName and unabbreviatedHierarchyName for a particular structural object class.

The exception is a value of hierarchyNameSpecification defined for the object class top. This value of hierarchyNameSpecification is the default rule used if a specific rule is not defined for a structural object class. The structuralObjectClass field identifies which object class the hierarchyNameSpecification value applies to.

The delimiter field identifies a character sequence to be used to separate components in the value of hierarchyName or unabbreviatedHierarchyName. The default is semicolon character.

The specification field is a sequence of structures that define specific RDNs in the DN to include in the constructed attribute. Each RDN is referenced by a positive numeric index relative to one of three reference points.

The reference points are:

- top the first RDN of the DN under the root entry. The offset from this point indexes towards the end of the DN. Thus, the reference top: 0 indicates the first RDN under the root entry.
- bottom the last RDN of the DN. The offset from this point indexes towards the start of the DN. Thus, the reference bottom: 1 indicates the second last RDN in the DN.
- autonomous this reference point is relative to the RDN of the autonomous administrative point which applies to the entry being evaluated. For example, in the

demonstration database Deltawing, the O "Deltawing" entry is an autonomous point. The hierarchyNameSpecification defined for the O "Deltawing" subschema area uses the O "Deltawing" entry as the point for evaluating the autonomous references, regardless of any superior entry in the DIT. The offsets relative to the autonomous point index towards the end of the DN.

The preferredAVA field in each specification structure is optional. It indicates the preferred attribute type to use in the constructed value when a selected RDN has more than one AttributeTypeAndValue in the RDN. The first attribute type in the list which corresponds to a type occurring in the RDN is selected. If none match, or the preferredAVA field is not specified, the first attribute in the RDN is selected.

The topBound and bottomBound provide limits on the RDN components selected. If a component selected by the specification field:

- is above the topBound or below the bottomBound, it is not used in the constructed value.
- matches the topBound or bottomBound, or is between the two bounds, it is used in the constructed value.

 $If {\tt hierarchyNameSpecification} is not provided in a subschema administrative area, the default behaviour for constructing hierarchyName and$

unabbreviatedHierarchyName matches the following hierarchyNameSpecification specification.

```
{
 structuralObjectClass top,
 topBound autonomous:0,
 bottomBound bottom:1,
 specification {
   {
   selection autonomous:1
  },
  {
   selection bottom:1
  }
 }
},
{
 structuralObjectClass organizationalUnit,
 topBound autonomous:0,
 bottomBound bottom:0,
 specification {
   {
    selection autonomous:1
   },
   {
    selection bottom:0,
```

```
preferredAVA {
    organizationalUnitName
    }
  }
}
```

updatersName

This operational attribute a text string derived from the RDN of the user who most recently modified a directory entry. As it is not automatically maintained by the DUA or DSA, the modifiersName attribute should be used in its place.

```
updatersName ATTRIBUTE ::= {
  SUBTYPE OF name
  WITH SYNTAX DirectoryString { ub-name }
  SINGLE VALUE TRUE
  NO USER MODIFICATION TRUE
  USAGE directoryOperation
  ID {vf 18 1}
}
```

viewDSMatchQuality viewDSSimpleMatchQuality

These attributes allow search results to be sorted according to how well they match a DUA's search filter. They have the following schema definitions:

```
viewDSMatchQuality ATTRIBUTE ::= {
 WITH SYNTAX INTEGER
 EQUALITY MATCHING RULE integerMatch
 ORDERING MATCHING RULE integerOrderingMatch
 SINGLE VALUE
                     TRUE
 USAGE
                     directoryOperation
 ID
                     { 1 3 6 1 4 1 21473 5 18 11 }
viewDSSimpleMatchQuality ATTRIBUTE ::= {
 WITH SYNTAX INTEGER
 EQUALITY MATCHING RULE integerMatch
 ORDERING MATCHING RULE integerOrderingMatch
 SINGLE VALUE
                     TRUE
 USAGE
                     directoryOperation
 ID
                     { 1 3 6 1 4 1 21473 5 18 12 }
}
```

Each entry in a search result has a value for viewDSMatchQuality and viewDSSimpleMatchQuality. They can be requested by a DUA so that it can sort the

results itself; or be referenced by a DUA through a sort control so that the DSA can sort the results.

If an entry matches the search filter exactly, then:

- viewDSSimpleMatchQuality equals 0
- viewDSMatchQuality equals 0

If an entry matches the search filter approximately, then:

- viewDSSimpleMatchQuality equals 1
- viewDSMatchQuality is greater than 0 the higher the value, the less well the entry matches the search filter.

Typically, a DUA issues a sort control that requests sorting on

viewDSSimpleMatchQuality first and then on the second search attribute (for example, surname). This would group the exact matches at the start of the results, followed by the approximate matches in alphabetical order.

viewDSSessionObject

This operational attribute stores session objects in the directory. It is automatically indexed for its equality matching rule and dn-tracking is enabled for it. This attribute should be included in the attributes replicated to another DSA if Access Presence traffic is load-balanced across a master and its replicas. The VMA will include it in the default set of attributes it offers when creating a new replication agreement.

```
The viewDSSessionObject operational attribute has the following
schema definition:
viewDSSessionObject AttributeTypeDescription ::= {
 identifier { 1 3 6 1 4 1 21473 5 18 20 },
            { printableString:"viewDSSessionObject" },
 name
 information {
  equalityMatch directoryStringFirstComponentMatch,
  attributeSyntax printableString:"SessionObject",
  multi-valued TRUE,
   application directoryOperation
 }
}
SessionObject ::= SEQUENCE {
 identifier PrintableString,
    -- Recommend use of a UUID in string representation
 created INTEGER,
    -- Unix style seconds since 1970-01-01T00:00:00
 subject DistinguishedName,
    -- Authenticated identity for this session
 remote UTF8String OPTIONAL
    -- Proxy authorization remote user identifier
}
```

unabbreviatedHierarchyName

This operational attribute is a string that holds a representation of an entry's superior units.

The DSA constructs the value from the entry's DN, and according to the specification in the hierarchyNameSpecification attribute that is in the subschema administrative area containing the entry.

The unabbreviatedHierarchyName attribute is displayed on a Search Form where:

- the forms component defines that an organizationalUnitName attribute should be displayed; and
- the hierarchyNameBehaviour component is set to unabbreviated.

If the entry can have subordinates, the DUA replaces the second component with the RDN of the entry itself. Both RDNs are abbreviated.

```
unabbreviatedHierarchyName ATTRIBUTE ::= {
  SUBTYPE OF name
  WITH SYNTAX DirectoryString { ub-name }
  SINGLE VALUE TRUE
  NO USER MODIFICATION TRUE
  ID {ads 4 0}
}
```

resolvedDistinguishedName

This is an integer corresponding to the internal 'entry identifier' used to tag every entry in the DSA. It is used in constructing an alias name of an entry which is much shorter than the entry's full Distinguished Name. A ViewDS DSA will return such an alias name if the DUA requests the attribute resolvedDistinguishedName in a search request, typically to reduce the amount of data transmitted in search results when operating over a slow network.

The attribute is predefined in the schema and is not user modifiable. It does not exist in any entry; it is used only as a signal to the DSA to return such short alias names and in constructing such alias names.

If this attribute is requested, then the DUA should also request the dontUseCopy service control for correct operation in the presence of replicated data.

```
resolvedDistinguishedName ATTRIBUTE ::= {
  WITH SYNTAX ResolvedDistinguishedName
  EQUALITY MATCHING RULE integerMatch
  SINGLE VALUE TRUE
  NO USER MODIFICATION TRUE
  USAGE dSAOperation
  ID {vf 18 0}
}
ResolvedDistinguishedName ::= INTEGER
```

Chapter 7: Printing DUA

The Printing DUA allows data to be extracted from a directory and formatted into reports, printed directories and formats suitable for other systems. The input to the Printing DUA is an input script – which can be selected by an Access Presence user to generate a report – and its output can be written to a file and displayed by Access Presence.

This chapter has the following sections:

- Running the Printing DUA
- Input script syntax
- Supported attribute syntaxes

Running the Printing DUA

The Printing DUA can be invoked from Access Presence (see <u>Configuring for printing</u>) or from the command line as follows:

```
pdua [ -t vfhome ] [ -a | -u username -p password ]
[ -b baseobject ] [ -r requestor ] [ -o address ]
[ -e errorfile ] [ -f outputfile ] [ inputfile ]
```

The command-line options are as follows:

-t vfhome

Sets the ViewDS root directory to vfhome instead of the environment variable f(VFHOME).

-a

Authenticates with the server using anonymous credentials.

-u username

Provides a username with which to authenticate with the DSA.

The username is either the value of a viewDSUserName attribute or a DN in Stream DUA notation enclosed in curly brackets. (For information about Stream DUA notation, see the *ViewDS Directory Server: Technical Reference Guide*.)

-p password

Provides a password with which to authenticate with the DSA.

-b baseobject

Sets the base object to a entry in the DIT from which the Printing DUA will generate a report. This option overrides the base-object option (see base) in the input script.

-r requestor

Enable proxy authorisation for each request sent to the DSA, using requestor as the identity that should be used to evaluate access controls.

-e errorfile

Sets the name of the file to which the Printing DUA writes error messages.

-f filename

Sets the name of the file for all normal output from the Printing DUA. When this option is unspecified, the Printing DUA writes output to the command line (stdout).

-o address

Connect to address instead of the address declared by the configuration-file parameter dsaAccessPoint or dsaAddress.

inputfile

The Printing DUA reads the input file containing a script. The script declares the entries and attributes to be extracted from the DSA, and the sorting parameters and the tags, text, and formatting to be inserted.

By convention, the input file has a name ending in the suffix ds; the output is directed to a file with the suffix do; and stderr if redirected goes to a file with suffix er.

Input script syntax

The input to the Printing DUA is a script specifying the content to be produced. The script consists of a list of parameters, some optional, some mandatory, that must be given in a fixed order. Each parameter begins on a new line and consists of a keyword, followed by a colon, a parameter argument, and a semi-colon.

The input language has the same extended Backus-Naur Form notation as the Stream DUA (see the *ViewDS Directory Server: Technical Reference Guide*):

- | separates alternative expressions
- () groups the enclosed expressions
- {} means zero or more repetitions of the enclosed expression
- [] means the enclosed expression is optional

These symbols are underlined if they form part of the syntax itself; the name of a production is shown in italic text; and literal text (e.g. a keyword) is shown in the font Courier New.

Script parameters

An input script consists of the following three groups of parameters in the order shown. Any text following the character # is a comment.

```
# Entry extraction parameters
base: name;
include_base: ( yes | no );
[depth: number;]
[exclude subtrees: filter;]
[select filter: filter;]
extract type: (matching | subtree);
preserve_hierarchy: ( yes | no );
# Entry ordering parameters
[class order: objectclass {, objectclass };]
[entry sort: class sort { class sort };]
# Data output parameters
[file start: string;]
entry output: objectclassoutput { objectclassoutput };
[file end: string;]
[data formats: format { format };]
```

Entry extraction parameters

The entry extraction parameters specify the region of the DIT (a subtree) from where data is to be extracted.

base

The mandatory parameter base specifies the name of the base entry of a subtree. It corresponds to the X.500 Search operation parameter <code>baseObject</code>.

```
base: name;
```

Where name is the full DN of an entry. For example:

```
base :
    organizationName "Deltawing"
    / organizationalUnitName "Research Laboratories"
    ;
```

include_base

The mandatory parameter include_base indicates whether the base entry should be included in the extraction.

```
include_base: ( yes | no );
```

For example:

include_base : yes;

depth

The optional parameter depth specifies the lower limit of the subtree. If it is unspecified there is no depth limit. A value of zero indicates the base entry.

depth: number;

The limit is specified as a 'distance' from the base of the subtree. The distance between the base entry and an entry subordinate to it is defined as the number of extra RDN terms in the DN of the latter. The subtree consists of the base entry and all of its subordinates which lie within the distance specified (including those which lie at the limit).

For example:

depth : 3;

exclude_subtrees

The optional parameter exclude_subtrees reduces the DIT subtree region defined by base, include base and depth by specifying subtrees to be excluded.

exclude_subtrees: filter;

where filter is in the form of an X.500 filter or an LDAP string representation of a filter enclosed in double quotes. Any entry matching the filter together with all of its subordinates will be excluded from the DIT region from which the data is to be extracted.

For example:

```
exclude_subtrees:
    not (objectClass = organizationalUnit or objectClass =
    organizationalPerson);
```

The parameters select_filter, extract_type and preserve_hierarchy specify the entries to be extracted and whether the hierarchical relationships between them are to be preserved.

select_filter

The optional parameter select_filter specifies a selection filter that helps define the set of entries to be extracted. If it is missing an empty filter is assumed. The parameter corresponds to an X.500 search filter or an LDAP string representation of a filter enclosed in double quotes. Together with extract_type, it specifies the criteria by which entries are selected for extraction.

```
select_filter: filter;
```

For example:

select_filter : objectClass = organizationalUnit;

extract_type

The mandatory parameter <code>extract_type</code> specifies how a <code>select_filter</code> is to be interpreted.

extract_type: (matching | subtree);

Where:

- matching the Printing DUA only extracts the entries within the search region satisfying the filter.
- subtree the Printing DUA extracts all entries within the search region satisfying the filter along with all entries between an entry satisfying the filter and the base entry. A value of subtree is not allowed if the hierarchy is not to be preserved – that is, preserve hierarchy is no.

For example:

extract_type : subtree;

preserve_hierarchy

The mandatory parameter preserve_hierarchy specifies whether the hierarchical relationships between the extracted entries are to be preserved.

preserve_hierarchy: (yes | no);

If set to no, the extracted entries are treated as a set of unrelated entries.

For example:

preserve_hierarchy : yes;

Entry ordering parameters

If the entry-extraction parameter preserve_hierarchy is set to:

- yes, the entries are extracted in preorder. An order may be specified for each set of entries with the same parent in the tree formed by the base entry and the extracted entries.
- no, the extracted entries are treated as a set of unrelated entries and an ordering may be specified. The following parameters specify ordering.

class_order

The optional parameter class_order specifies the order of the object classes of the extracted entries. If the hierarchy is preserved (i.e. preserve_hierarchy) is yes, then sorting by object class occurs for each set of entries which have the same parent in the tree formed by the base entry and the extracted entries. If no class order is specified then sorting by object class does not occur. Its argument is a list of object class names.

class_order: objectclass {, objectclass };

For example:

class_order : organizationalPerson, organizationalUnit;

entry_sort

The optional parameter <code>entry_sort</code> specifies the sorting criteria for the extracted entries. If <code>class_order</code> was specified then this specifies the order of the entries within each object class. If the hierarchy is preserved (i.e. <code>preserve_hierarchy</code>) is <code>yes</code>, then sorting occurs for each set of entries which have the same parent in the tree formed by the base entry and the extracted entries. The parameter is specified as a list of attribute type information for each object class. The first attribute type is the primary sort key, the second the secondary, etc.

entry sort: class sort { class sort };

class_sort is a specification of the sorting criteria for a particular object class. It has the form:

class sort ::= [objectclass : fieldspec {, fieldspec }];

fieldspec is used to specify the attribute types to sort on. This may be an attribute in the current entry represented by type, or it may be an attribute in another entry referred to by a DistinguishedName value stored in an attribute in the current entry. This is represented by type.type where the first *type* must be an attribute in the current entry with a syntax of DistinguishedName and the second *type* is an attribute in the referenced entry.

fieldspec ::= type | type . type ;

Where an attribute used as a sort key has multiple values then only the first value retrieved is used for the sort. Attributes of a particular type are sorted in ascending order according to the ordering rule for that type.

For example:

```
entry_sort :
    [ organizationalPerson : sortSubs, surname, givenName ]
    [ organizationalRole : sortSubs, roleOccupant.surname,
    roleOccupant.givenName ];
```

Data output parameters

These parameters specify the data to be extracted from the selected entries and how this data should be outputted.

file_start

The optional parameter file_start specifies the text string to be placed at the beginning of the file.

file start: string;

For example:

file start : "Current list of units\n\n";

entry_output

The mandatory parameter entry_output specifies the data to be output and the way in which it is to be written. Each object class to be output must be represented by an output specification which describes how an entry belonging to the object class is to be output. The syntax is

```
entry_output: objectclassoutput { objectclassoutput } ;
objectclassoutput ::= [ objectclass [+] :
```

```
entrystart , { { datastart , datatype , dataend }} , entryend ]
datatype ::= typespec [+] [ ( number ) ] | typespec [+] [ ( [
rdnSelect , ] number ) ] | subordinate | path
```

The items <u>subordinate</u> and <u>path</u> are described below.

```
typespec ::= type [ . componentspec ] | type . type [. componentspec
]
componentspec ::= component { . component }
```

typespec is used to identify the attribute type to display. This may be an attribute in the current entry or it may be an attribute in an entry referenced by a DistinguishedName value in an attribute of the current entry. For example, to display the surname attribute of the entry pointed to by the roleOccupant attribute of an organizationalRole object class, the following objectclassoutput could be used:

[organizationalRole: "", roleOccupant.surname, ""]

componentspec is an optional extra information which may be used to extract fields from complex attribute syntaxes. e.g. to print out the telephoneNumber field in a facsimileTelephoneNumber, the following typespec could be used: facsimileTelephoneNumber.telephoneNumber

The component may be used to access a named field in structure (as above), or it may be a number providing an index into a SEQUENCE OF or SET OF list where the first element in the list has an index of 1. Using an index value of zero will cause the number of elements in the list to be output. Using a negative index will reference elements from the end of the list – for example, -1 will reference the last element in the list.

entrystart, datastart, dataend and entryend are each defined as string. Each of these must be present even if empty. If the # character occurs in one of the strings, it is replaced with a number corresponding to the depth of the entry i.e. the distance between the entry and the base entry. This special meaning can be overridden by preceding the # with the escape character \.

If datastart or dataend begins with a *, the * is not output but indicates that the remainder of the string should be output even if the associated attribute is not present in the entry.

There are two ways to output attributes with multiple values: either only the 'first' value is output or else all the values are output. The output of multi-valued attributes is controlled by the following:

- if a + is appended to the object class name then all values of the listed attributes will be output,
- if a + is appended to the name of an attribute then all the values of that attribute will be output,

- if an attribute is specified more than once for a particular object class then all the values of that attribute will be output,
- if none of the above apply for a particular attribute then only the 'first' value will be output.

An attribute may be specified more than once for a particular object class to cater for the attribute having more than one value. Where an attribute is specified more than once, all the specifications must be contiguous. If an attribute to be output has two values then the second value may be output in a different way to the first value by a second output specification for the attribute. If a second specification is not present then the second occurrence of the value is output in the same way as the first. In general, if an attribute to be output has n values then the kth value, where 1 < k = n, is output as specified in the kth occurrence of the attribute in the output statement, or if such a statement is not present, it is output as specified in the last occurrence of the attribute in the output statement.

If an attribute to be output has attribute syntax of either BOOLEAN or

DistinguishedName then it may be accompanied by a set of arguments which control the presentation of the value(s). These arguments are described later in the chapter.

For example:

```
entry_output :
  [ organizationalUnit : "*# ",
  {"", organizationalUnitName, ""}
  {"\nMgr: ", manager, ""}
  , "\n\n"]
;
```

file_end

The optional parameter ${\tt file_end}$ specifies the text strings to be placed at the end of the file.

file_end: string;

data_formats

The optional parameter data_formats contains a list of formatting instructions for attributes with attribute syntax BOOLEAN, attributes with attribute syntax DistinguishedName and for path information. The syntax is

```
data_formats: format { format };
format ::= formatBool | formatDN | formatSubordinate
```

Each format item in the list contains a complete formatting instruction.

A formatBool item is a formatting instruction for attributes with attribute syntax BOOLEAN.

A formatDN item is a formatting instruction for attributes with attribute syntax DistinguishedName and for path information. A formatSubordinate item is a formatting instruction for subordinate object classes. The first argument in each formatting instruction is the reference number of the item. This is the value used in the <code>entry_output</code> parameter to refer to a particular format.

formatBool

The syntax for formatBool is

```
[ number : TRUEstring , FALSEstring ]
The items TRUEstring and FALSEstring are each a string.
```

TRUEstring specifies the string to be output if the value is TRUE; FALSEstring specifies the string to be output if the value is FALSE. If a BOOLEAN value is to be output and no formatting instruction is given, these values default to "Y" and "N" respectively.

formatDN

The syntax for formatDN is

```
[ number : [ compress , ] [ reverse , ] sepRDN , startRDN , endRDN,
sepAVA [ , sepTV ] ]
```

The items sepRDN, startRDN, endRDN, sepAVA and sepTV are all strings.

The second argument indicates whether the extracted information should be abbreviated. If compress is specified then the information will be abbreviated; otherwise, it will be output normally. Only values of type <code>organizationalUnitName</code> may be abbreviated.

startRDN indicates whether the extracted RDNs are to be output in normal order (with the first RDN being the closest to the root) or in reverse order (with the first RDN being furthest from the root). If reverse is specified then the RDNs are output in reverse order; otherwise they are output in normal order.

sepRDN specifies a text string to separate the RDNs. In the case where an RDN has more than one AVA, startRDN specifies a text string to be placed on the left hand side of the RDN, endRDN a text string to be placed on the right hand side, and sepAVA a text string to separate the AVAs. The final argument sepTV specifies a text string to separate the type and value strings in each AVA. This last argument is optional - if it is omitted then only the attribute value of each AVA will be output. If a DN or path value is to be output and no formatting instruction is given, these values default to ", ", "(", ")", ", " and "=" respectively.

The syntax for formatSubordinate is:

```
formatSubordinate ::= [ number : formatSubClass { , formatSubClass }
]
formatSubClass ::= { object_class : start_string , end_string }
```

The start_string is printed before the first subordinate with object class object_ class of the current entry and the end_string is printed after the last subordinate with the object class object_class of the current entry. The start_string and end_string are only printed if the current entry has at least one subordinate of the defined object class. A formatSubordinate data format is only used in conjunction with a <code>%subordinates</code> typespec. For example:

```
data_formats : [ 1: " | ", "", "", ""]
[ 2: "YES", "NO"] ;
[ 3: { organizationalUnit: "<UNIT>", "</UNIT>" },
{ organizationalRole: "<ROLE>", "</ROLE>" } ]
```

Subordinates

The *%subordinates* 'pseudo-attribute' may be used as a place holder to indicate where the current entries' subordinate information should be printed relative to the attribute information of the entry. If not present, the subordinate information is printed after the entryend string of the entry.

The %subordinates directive may have an optional format identifier which may be used to reference a data_format which may be used to specify extra formatting information for each subordinate object class.

```
subordinates ::= %subordinates [ ( number ) ]
```

Path data

In addition to attribute information, information from an entry's Distinguished Name may also be output. This is accomplished by the definition of the "pseudo-attribute" *%path. %path* represents the Distinguished Name of the entry being written to output. It permits the entry's Distinguished Name to be treated as if it were an attribute.

%path may be specified any number of times for a particular object class in the entry_output parameter. Unlike the case for ordinary attributes, multiple instances do not have to be contiguous. Also there is no special meaning attached to the instances after the first one; each instance is processed individually.

Distinguished Name output

The output of distinguished names (i.e. attributes which have attribute syntax of DistinguishedName and of *path* information) is controlled by a pair of optional arguments. An attribute that has the attribute syntax of DistinguishedName is specified as follows in the entry output parameter:

```
type [+] [ ( [ rdnSelect , ] number ) ]
```

Path information is specified as follows in the entry_output parameter:

%path [([rdnSelect ,] number)]

The first argument, rdnSelect indicates the RDNs to be extracted. It has the form:

```
rdnSelect ::= all | selector | selector selector [ ( [ - ] number ) ]
selector ::= number | $ [ - number ] | @ [ + number ]
```

A value all indicates that all the RDNs in the distinguished name are to be extracted.

A value k where k is an integer indicates that the kth RDN is to be extracted, where $1 \le k \le ($ the number of RDNs in the distinguished name).

A value of '\$' indicates the last RDN while a value of "\$ - k" where $1 \le k \le$ (the number of RDNs in the distinguished name - 1) indicates the RDN at distance k from the last RDN. If the entry represented by the distinguished name being processed is a subordinate of the base entry then a value of "@" indicates the RDN of the base entry while a value of "@ + k" where $1 \le k \le$ (the number of RDNs in the distinguished name - the number of RDNs in the distinguished name of the base entry.

If two selectors are entered, then they specify a subset of the distinguished name. If the distinguished name is considered as a sequence of RDNs with the first RDN being the one closest to the DIT root, then the subset is the contiguous subsequence of RDNs starting at the RDN represented by the first selector and ending at the RDN represented by the second (i.e. the selectors define the end points of the subsequence).

If for an entry the RDN representing the first selector is further from the DIT root than the RDN representing the second then the subsequence is null.

If the selectors in rdnSelect are not accompanied by a number in parentheses, then the subsequence defined by them is extracted. Otherwise, a maximum of number RDNs are extracted where number is a non-zero positive integer.

If number is not preceded by a minus sign, then only the first number RDNs of the subsequence are extracted (if there are less than number RDNs in the subsequence then they are all extracted). If number is preceded by a minus sign, then only the last number RDNs of the subsequence are extracted.

If the entry represented by the distinguished name being processed is not a subordinate of the base entry and a selector of either "@" or "@+k" has been specified, then the following action is taken:

- The entire rdnSelect argument is ignored i.e. all the RDNs in the distinguished name are extracted;
- A warning message is placed in the error file.

The message is:

WARNING - attribute xx for following entry has distinguished name value outside of selected range: dd

where xx is the name of the attribute which possesses the distinguished name value and dd is the Distinguished Name of the entry which has the attribute.

NOTE: The above condition can only arise in the processing of an attribute which has attribute syntax of DistinguishedName. It cannot arise in the processing of %path.

If the value of rdnSelect is a single selector which is not in the allowable range then no data is extracted.

If two selectors are specified and one or both of the selectors are outside the allowable range then:

- If the second selector is k where k > (the number of RDNs in the distinguished name) or is @
 + k where k > (the number of RDNs in the distinguished name the number of RDNs in the
 distinguished name of the base entry) then it is processed as if it were "\$". If the first selector
 has this property then no RDNs are extracted.
- If the first selector is "\$ k" where k > (the number of RDNs in the distinguished name 1) then it is processed as if it were "1". If the second selector has this property then no RDNs are extracted.

The second argument controlling the output of a distinguished name is a number indicating which formatting statement in data_formats is to be used for formatting the extracted data. This argument must be present.

The first argument, rdnSelect is optional. If it is not provided then the entire distinguished name is extracted. If both arguments are omitted, the entire distinguished name is output using the default formatting.

For example:

%path(@+1 \$-1 (2), 1)

Parameter-value definitions

string

A string is any sequence of characters enclosed in matching single or double quotation marks. The opening and closing quotes of the string must be on the same line. If the string contains a quote of the same type as the enclosing quotes then the embedded quote must be escaped by duplicating it in the string. For example, the string value O'Hara could be quoted as 'O''Hara' (the " is two single quotes) or "O'Hara".

Note that text strings specified in the script may contain non-printable characters as well as printable ones. Non-printable characters are represented using a backslash followed by either a special character or a three-digit octal code for the character. The supported special characters are \n (linefeed), \t (tab), \\ (backslash), \' (single quote), and \" (double quote).

number

A sequence of digits.

objectclass

An objectclass is the name of an object class (either X.500 or View500 built-in, or a user-defined name specified via an objectClasses operational attribute), or an object identifier. An object identifier may be optionally preceded by the keyword class.For example:

```
organizationalUnit
deltawingOrgPerson
{1 3 32 0 1 6 23}
```

Supported attribute syntaxes

The Printing DUA converts attributes with a complex syntax into simple text strings. It supports the following subset of the attribute syntaxes supported by the DSA:

BOOLEAN DirectoryString DistinguishedName FacsimileTelephoneNumber GeneralizedTime INTEGER NumericString ORAddress ORName PostalAddress PrintableString TeletexString TeletexString TelexNumber UTCTime

Chapter 8: Printing DUA scripts

ViewDS includes several scripts for extracting information from the demonstration directory, Deltawing. These scripts can be adapted for any other directory and serve as a starting point for developing new scripts.

The following are supplied scripts:

phonelist.ds	Simple phone list for an organizational unit giving name, unit and phone number for all staff in the unit.
unitlist.ds	List of organizational units, with address, phone and fax number.
executivelist.ds	List of all persons whose job title begins with 'A/C Executive' with name, phone and job title.
mailinglist.ds	List of all persons whose mailing address does not include the word 'Australia', with name, title and mailing address.
staffdetails.ds	List of all persons with most of their attributes, and all fields tagged (for importing into a desktop publishing package).

phonelist.ds

This script produces a simple phone list giving the name, unit and phone number for each person in an organizational unit.

Input script

```
# This script produces a phone list. The name, and phone number
# of each person are given as well as the units they belong to.
base :
    organizationName "Deltawing"
    / organizationalUnitName "Deltawing Information Systems Ltd."
    / organizationalUnitName "Home Media Division"
    ;
```

```
# This parameter has no role in this case. Setting is arbitrary.
include base : no ;
# Select all people
select_filter :
 objectClass = organizationalPerson ;
# Extract only entries matching filter
extract type : matching ;
# Don't preserve hierarchical relationships between extracted entries
preserve hierarchy : no ;
# Sort by Surname, Given name, Telephone number
entry sort :
 [ organizationalPerson : surname, givenName, telephoneNumber ];
# Header on output file
file start : "Phone List\n\n" ;
# Data output
entry output :
 # Output instructions for each person
 [ organizationalPerson : "",
  # Surname
 { "", surname, ""}
  # Comma then space then given name then tab
 { ", ", givenName, *"\t"}
  # Two units immediately after "base", then tab
 { "", %path(@+1 $-1 (2), 1), *"\t"}
 \ensuremath{\texttt{\#}} All telephone numbers - separated by comma space
 { "", telephoneNumber, ""}
 { ", ", telephoneNumber, ""}
  # Terminate line
  , "\n" ]
  ;
# Output format of the two superior units selected above
data formats :
  # Compress the names of the units and separate them with comma
 [ 1: compress, ",", "", "", ""]
 ;
```

Sample output of phonelist.ds

Briggs,	RobertHomeEd	(03)	9335	7132
Brkic,	JohnHomeEd,MarkRes	(03)	9335	3145
Bruce,	MartinaWWWS,StratRelat	(03)	9335	4647
Budgen,	RonaldHomeEd,MarkRes	(03)	9335	3131
Campbell,	RodneyHomeEd,MarkRes	(03)	9335	8968
Cassio,	SuzyHomeEd,MarkRes	(03)	9335	8882
Chan,	TimHomeEd,MarkRes	(03)	9335	8356
Cheep,	CarolWWWS,WebDev	(03)	9335	4224
Clifford,	RobertHomeEd,MarkRes	(03)	9335	3167
Colenutt,	GaryHomeEd,MarkRes	(03)	9335	3177
Corbet,	MeredithWWWS	(03)	9335	4526
Crompton,	PeterHomeEd,MarkRes	(03)	9335	1435
Crowhurst,	DerekHomeEd,MarkRes	(03)	9335	3967
Cullen,	GregHomeEd,MarkRes	(03)	9335	6780
Dang,	EmHomeEd,MarkRes	(03)	9335	8720

unitlist.ds

This script produces a list of units in hierarchical order together with the location and telephone and fax numbers for each unit.

Input script

```
# This script produces a list of units in hierarchical order.
# The location, telephone number and facsimile telephone
# number of each unit are also output.
# Specify base unit
base :
    organizationName "Deltawing"
    / organizationalUnitName "Deltawing Automotive Ltd."
    / organizationalUnitName "Avalon Factory"
    ;
# Include base unit in search
include_base : yes;
# Select all units
select_filter : objectClass = organizationalUnit;
# Extract entries satisfying above filter together with the units
```

```
# they belong to
extract type : subtree;
# list units in hierarchical order
preserve hierarchy : yes;
# Units with the same parent are to be sorted in the same way
# as in the on-line system
entry sort :
 [ organizationalUnit : SortSubs, OrganizationalUnitName]
 ;
# Header on output file
file start : "Current list of units\n\n";
# Data output
entry output :
 # Output instructions for each unit ...
  # Asterisk followed by "level" of unit followed by space
 [ organizationalUnit : "*# ",
  # Unit name
  {"", organizationalUnitName, ""}
  # Linebreak followed by label followed by location
  {"\nAdd: ", location, ""}
  # Linebreak followed by label followed by telephone number
  {"\nTel: ", telephoneNumber, ""}
 # Linebreak followed by label followed by facsimile telephone number
  {"\nFax: ", facsimileTelephoneNumber, ""}
  # Terminate the current line and follow with a blank line
  , "\n\n"]
  ;
```

Sample output of unitlist.ds

```
*2 Operations
Add: 74 Deltawing Road One, Lara, Victoria, 3122
Tel: (052) 35 6934
Fax: (052) 35 2178
*3 Operations Support
Add: 74 Deltawing Road One, Lara, Victoria, 3122
Tel: (052) 35 4541
Fax: (052) 35 4593
...
```

executivelist.ds

This script produces a list of all persons whose job title begins with 'A/C Executive' with name, phone and job title.

Input Script

```
# This script produces a list of A/C Executives.
base :
 organizationName "Deltawing"
  :
# This parameter has no role in this case. Setting is arbitrary.
include base : no ;
# Select all people with title "A/C Executive"
select filter :
 objectClass = organizationalPerson and title ~ "A/C Executive"
 ;
# Extract only entries matching filter
extract type : matching ;
# No hierarchical relationships between extracted entries
preserve hierarchy : no ;
# Sort by telephone number, surname then given name
entry sort :
  [ organizationalPerson : telephoneNumber, surname, givenName ]
  ;
# Header on output file
file_start : "List of A/C Executives\n" ;
```

```
# Data output
entry_output :
    # Output instructions for each person ...
    [ organizationalPerson : "",
    # Attributes separated by tabs
    { "", telephoneNumber, *"\t"}
    { "", surname, *"\t"}
    { "", surname, *"\t"}
    { "", givenName, *"\t"}
    { "", title, ""}
    # Terminate line
    , "\n" ]
;
```

Sample output of executivelist.ds

(07) 362 8090 BonnettGloria A/C Executive : Far North Queensland
(07) 362 8090 MicallefAlfred A/C Executive : Northern NSW
(09) 445 5034 MariebelCarole Sales Executive : South Australia
(09) 445 5055 BalmzianNoshik Sales Executive : Western Australia
(09) 445 5071 BrownRoxanna A/C Executive : Perth Region
+1-212-667-9577 PintoCristino A/C Executive : North East
+1-212-667-9578 CostaCarmello A/C Executive : North West

mailinglist.ds

This script produces a list of all persons whose mailing address does not include the word 'Australia', with name, title and mailing address.

Input script

```
# This script produces a mailing list for the library.
base :
    organizationName "Deltawing"
    /organizationalUnitName "Deltawing Automotive Ltd."
    ;
# Omit base
include_base : no ;
# Select all overseas staff
```

```
select filter:
 objectClass = organizationalPerson and
 not ( mailingAddress = * "Australia" * )
 ;
# Extract only entries matching filter
extract type : matching;
# Don't preserve hierarchical relationships between extracted entries
preserve hierarchy : no ;
# Data output
entry output :
  # Output instructions for each staff
  # Blank line
  [ organizationalPerson : "\n",
  # Attributes in the form of label followed by space followed by value
  { *"Name: ", givenName, *" "}
  { *"", surname, *"\n"}
  { *" ", title, *"\n"}
  { *"Post: ", mailingAddress, *"\n"}
  # Terminate line
  , "\n" ]
  ;
```

Sample output of mailinglist.ds

```
...
Name: Carmello Costa
    A/C Executive : North West
Post: Deltawing USA Ltd, 115 Fifth Avenue, New York, NY 10003
Name: Veronica Brennan
    Sales Administration : California
Post: Deltawing USA Ltd, 115 Fifth Avenue, New York, NY 10003
Name: Marie Gander
    A/C Executive : South West
Post: Deltawing USA Ltd, 115 Fifth Avenue, New York, NY 10003
...
```

staffdetails.ds

This script produces a list of all persons with most of their attributes, and all fields tagged (for importing into a desktop publishing package).

Input script

```
# This script outputs most attributes for units and people.
base :
 organizationName "Deltawing"
 / organizationalUnitName "Deltawing Information Systems Ltd."
 / organizationalUnitName "Applications Development"
 ;
# Include base
include base : yes ;
exclude subtrees:
 # Exclude entries which are not units or people and all
 # entries under them
 not (objectClass = organizationalUnit
 or objectClass = organizationalPerson)
 ;
# Setting is arbitrary in this case as a subtree is extracted anyway
extract type : subtree ;
# Preserve hierarchical relationships between extracted entries
preserve hierarchy : yes ;
# Where extracted entries have the same parent unit, output people first
# then units.
class order : organizationalPerson, organizationalUnit;
entry sort :
  # Units with the same parent are to be sorted in the same way as in
  # the on-line system
 [ organizationalUnit : sortSubs, organizationalUnitName ]
  # People with the same parent are to be sorted in the same way as in
  # the on-line system
 [ organizationalPerson : sortSubs, surname, givenName ]
  ;
# Data output
entry output :
 # Output instructions for each unit ...
  # Line break
 [ organizationalUnit : "\n",
  # Tag (backslash followed by "level" of unit followed by U) followed
  # by unit name
  { *"\\#U", organizationalUnitName, ""}
  # All attribute values output as tab followed by tag followed by
```

```
# attribute value
{ "\t\\L", location+, ""}
{ "\t\\T", telephoneNumber+, ""}
{ "\t\\F", facsimileTelephoneNumber+, ""}
{ "\t\\K", keylinkAddress+, ""}
{ "\t\\E", emailAddress+, ""}
{ "\t\\X", telexNumber+, ""}
{ "\t\\Y", teletexTerminalIdentifier+, ""}
# Terminate line
, "\n" ]
# Output instructions for each person ...
[ organizationalPerson : "",
# Common name
{ *"\\C", commonName, ""}
# All attribute values output as tab followed by tag followed
# by attribute value
{ "\t\\S", surname, ""}
{ "\t\\G", givenName+, ""}
{ "\t\\L", location+, ""}
{ "\t\\T", telephoneNumber+, ""}
{ "\t\\F", facsimileTelephoneNumber+, ""}
{ "\t\\K", keylinkAddress+, ""}
{ "\t\\E", emailAddress+, ""}
{ "\t\\X", telexNumber+, ""}
{ "\t\\0", mobileNumber+, ""}
{ "\t\\P", pagerNumber+, ""}
{ "\t\\Y", teletexTerminalIdentifier+, ""}
# Terminate line
, "\n" ]
;
```

Sample output of staffdetails.ds

• • •

```
\CFrank Nitzsche\SNitzsche\GFrank\L28th Floor, 74 King Street, Melbourne,
Victoria, 3000\T(03) 9335 8654\F(03) 9335 7800
\CAnna Palozzi\SPalozzi\GAnna\L28th Floor, 74 King Street, Melbourne,
Victoria, 3000\T(03) 9335 8534\F(03) 9335 7800
\CBarbara Ryan\SRyan\GBarbara\L28th Floor, 74 King Street, Melbourne,
Victoria, 3000\T(03) 9335 8514\F(03) 9335 7800
\CEnnio Torresan\STorresan\GEnnio\L28th Floor, 74 King Street, Melbourne,
Victoria, 3000\T(03) 9335 1423\F(03) 9335 7800
\CJacqueline Turner\STurner\GJacqueline\L28th Floor, 74 King Street,
Melbourne, Victoria, 3000\T(03) 9335 8760\F(03) 9335 7800
```

Chapter 9: Advanced features

This chapter describes several advanced Access Presence features, and includes the steps to configure for them.

It includes the following:

- Configuring proxy authorization for SSO
- <u>Configuring external SAML authentication</u>
- Configuring related-entry workflow
- <u>Configuring the approval process</u>
- Configuring for two-factor authentication

Configuring proxy authorization for SSO

Proxy authorization facilitates SSO (single sign on). That is, when a user logs on to their computer, through Windows for example, they also log onto ViewDS automatically. This streamlines 'self service' and there is no need to maintain a separate set of passwords for ViewDS users.

What is proxy authorization


Proxy authorization is a process where ViewDS assigns privileges based on logon information passed to it by an external agent, rather than its own authentication mechanism.

The external agent is usually a web server, which passes the logon information to Access Presence through an environment variable that uniquely identifies an entry in the directory. The name of the environment variable is set by the configuration-file parameter <u>webRemoteUser</u> which by default is REMOTE_USER.

The proxy authorization process uses mechanisms defined in *IETF Standard RFC* 3875 – The Common Gateway Interface (CGI) Version 1.1; and *IETF Standard RFC* 4370 – Lightweight Directory Access Protocol (LDAP) Proxied Authorization Control.

How proxy authorization works

The following illustration is an overview of how proxy authorization works.



The steps in the above illustration are described below:

1. The user logs onto Windows and requests an Access Presence page.

The web server recognises that the requested page requires authentication, and communicates with the client computer to confirm who is logged on.

The choice of authentication mechanism is a configuration option of the web server. Possible options include SSPI (Windows authentication), Netegrity SiteMinder or HTTP basic authentication.

- 2. The web server sends the page request to Access Presence, and sets the environment variable REMOTE_USER to the user's system-authentication ID.
- 3. Access Presence connects to the directory as the user that has been designated the 'proxy user'. It then searches the directory for the entry whose authorization attribute matches the value of REMOTE_USER. (An attribute is designated the authorization attribute during configuration for proxy authorization. It must be set to the user's system-authentication ID.)
- 4. If the search matches a single entry, the DSA returns the user's Distinguished Name (DN). Otherwise, the DSA returns nothing and Access Presence uses an empty DN to represent an anonymous user.
- 5. Access Presence communicates with the DSA to obtain information for the requested page. (This is restricted according to the privileges of the DN obtained in the previous step.)
- 6. Access Presence returns the resulting web page to the web server.
- 7. The web server passes the page to the browser.

Requirements

There are several requirements for proxy authorization:

- An authorization attribute must be selected to identify each directory user by their systemauthentication ID.
- The web server used with Access Presence must support an authentication process and be able to publish the system-authentication ID to the environment variable REMOTE_USER.
- The browser used must support the same authentication mechanism as that used in the web server.
- To allow 'self service', your installation of ViewDS must implement Basic Access Control (BAC).

Implementing proxy authorization

Implementing proxy authorization involves modifying the ViewDS <u>configuration file</u> and web server used by Access Presence:

- 1. Select an authorization attribute to identify each directory user by their system-authorization ID.
- 2. Set the configuration-file parameter webProxyUser to on. (If the parameter is not included in the configuration file, add it.)

webProxyUser = on

 Set the configuration-file parameter webProxyAuthAttribute to the name of the authorization attribute (the attribute you selected to store system-authentication IDs).
 For example:

webProxyAuthAttribute = uid

- 4. Set each authorization attribute to the appropriate system-authentication ID. For example, with Active Directory, the value is <domain>\<samAccountName>.
- 5. Create a directory user to be the 'proxy user'.
- 6. Add the operational attribute proxyAgent to the entry for the 'proxy user' (see the help topic Add an attribute to an entry).
- 7. Set the configuration-file parameter webProxyUser to the user name and password of the 'proxy user'.

For example:

```
webBindUser = vfsuper passwd
```

8. Set up your web server for authentication. For Microsoft IIS, enable any of the authentication modes for the Access Presence pages. For Apache, set up SSPI authentication for example.

Configuring external SAML authentication

SAML authentication, much like proxy authorization (described above), facilitates 'single sign on', allowing a user to access multiple services with a single log-in.

What is SAML authentication

Security Assertion Markup Language (SAML) is an XML-based, open-standard data format for exchanging authentication and authorization data between parties, in particular, between an identity provider and a service provider.

It is most commonly used for web browser 'single sign on' (SSO).

The SAML specification defines three roles: the principal (usually a user), the Identity provider (IdP), and the service provider (SP). In the use case addressed by SAML, the principal requests a service from the service provider and the service provider requests and obtains an identity assertion from the identity provider. On the basis of this assertion, the service provider can make an access control decision – in other words it can decide whether to perform some service for the connected principal.

Requirements

Access Presence implements the SAML2 Web SSO profile, acting as the service provider. It will use the HTTP Redirect binding for SAML authentication requests and expects the SAML response to be provided using the HTTP Post binding. At present, it only supports the X.509 Certificate representation of public key information in the XML signature.

Access Presence expects an identity to be provided in the NameID element of the SAML2 assertion's Subject element. It will map the NameID to an identity in the directory using the attribute identified by the webproxyauthattribute configuration file option. It does not currently care what the NameID Format attribute is set to, but assumes the NameID content is a simple string.

SAML2 authentication can only be enabled when Access Presence is using directory-based Session management. The presence of the websamlentity configuration-file parameter enables SAML2 authentication; although the websamlidpurl and websamltrustanchor configuration-file parameters must also be provided.

Implementing external SAML authentication

Implementing SAML authentication involves modifying the ViewDS <u>configuration file</u> used by Access Presence:


- 1. Set the configuration-file parameter websamlentity to the URI the identifies your Access Presence service provider.
- 2. Specify the URL of the SAML2 identity provider authentication endpoint in the websamlidpurl configuration-file parameter.

- 3. Save a copy of the SAML identity provider's signing certificate in the Access Presence configuration files.
- 4. Set the configuration-file parameter websamltrustanchor to the file name of the copy of the SAML identity provider's signing certificate.
- 5. Set the configuration-file parameter webProxyAuthAttribute to the name of the authorization attribute (the attribute you selected to store system-authentication IDs). For example: webProxyAuthAttribute = uid
- 6. Configure the SAML2 IdP.
- 7. If required by the SAML identity provider, add the call-back URL for Access Presence to the configuration-file parameter websamlendpoint.

Configuring related-entry workflow

An organization might have a policy that allows multiple entries for the same person. The policy might allow one actual entry for the person and several references to this entry were each represents, for example, a different role the person fulfils.

For example, consider a policy that involves <code>organizationalPerson</code> and <code>organizationalRole</code> entries. It allows each employee to have just one <code>organizationalPerson</code> entry, but this can be referenced by several <code>organizationalRole</code> entries to represent the employee's roles in the organization. This is illustrated below.



The related-entry workflow encourages a user to comply with the required policy when they create a new entry for someone who already has an entry. When a user adds a new entry for the above organizationalPerson, the workflow is as follows:

- 1. Access Presence presents the user with a Search Form (the particular Search Form can be specified).
- 2. The user searches for 'John Self'.

- 3. The Search Results page (specific to the related-entry workflow) lists all entries that fit the search criteria, and displays a button next to each that allows the user to create a new organizationalRole to reference the entry. The page also gives the user the option to create a new organizationalPerson entry if there is no existing appropriate entry.
- 4. The user creates a new organizationalRole for an entry. Access Presence automatically populates the new entry's attributes with the user's search criteria (so they don't have to enter the same information twice).
- 5. Access Presence adds a related-entry link to the new organizationalRole entry, to all existing organizationalRole entries, and to the organizationalPerson entry.

Implementing the related-entry workflow

- 1. Optionally, define a new Search Form to be used in the related-entry workflow. You can define a Search Form through the ViewDS Management Agent (see the help task *Create a Search Form*).
- 2. From the ViewDS Management Agent, perform the help task *Define related entries for the required object class*. (In the above example, related entries would be defined for the organizationalPerson object class.)
- 3. Optionally, if a template should be used instead of the Search Form template during the related-entries workflow, declare the template in the configuration-file parameter <u>webRelatedSearchTemplate</u>.
- 4. Optionally, if a template should be used instead of the Search Results template during the related-entries workflow, declare the template in the configuration-file parameter <u>webRelatedSearchResultTemplate</u>.

Configuring the approval process

This mechanism imposes an approval process on changes to the directory.

A user is designated either a 'requestor' or an 'approver'. A requestor can submit a request to add, modify, delete or move an entry. Later, a user with appropriate access rights, an approver, can either approve or reject the request.

Using the approval process

The approval process applies when a requestor modifies, deletes, moves or adds a subordinate to an entry. The following three example scenarios describe the approval process from a user's perspective.

Request modify

1. A requestor views an entry on the Expanded Entry page, which includes the 'Request modify' link (see <u>VFRequestModifyHref</u>). Note that this link is only displayed to requestors.

- 2. The requestor clicks the 'Request modify' link. The Modify page is displayed, which contains the 'Request reason' box and the attributes that can be modified by a requestor.
- 3. The requestor enters the new attribute values and the reason for their request, and submits the request.
- 4. Later, an approver is presented with a list of pending requests (see <u>VFRequestList</u>).
- 5. The approver clicks the request and the Modify page displays the requestor's changes and the reason for the modification. The page also includes 'Reject' and 'Approve' buttons (the default presentation of these buttons can be modified through the format file see the <u>Approval process tags</u>).

Request single entry delete

- 1. A requestor views an entry on the Expanded Entry page.
- 2. The requestor clicks the 'Request delete' link (see <u>VFRequestDeleteHref</u>). The Request Remove Entry page is displayed (see page 1) which contains the 'Request reason' box.
- 3. The requestor enters their reason and submits the request.
- 4. Later, an approver is presented with a list of pending requests (see <u>VFRequestList</u>).
- 5. The approver clicks the request and the Request Remove Entry page is displayed, this time showing the reason for the request along with the 'Reject' and 'Approve' buttons.

Request move

- 1. A requestor adds several entries to the target-object cache and then views another entry on the Expanded Entry page.
- 2. The requestor clicks the 'Request move' link (see <u>VFRequestMoveHref</u>). The <u>Select</u> <u>Target Object</u> page displays the entries in the target-object cache that are valid possible superiors to the entry, along with the 'Request reason' box.
- 3. The requestor enters their reason, selects a new superior and then submits the request.
- 4. Later, an approver is presented with a list of pending requests (see <u>VFRequestList</u>).
- 5. The approver clicks the request and the Select Target Object page is displayed, this time showing:
 - the reason for the request
 - the 'Reject' and 'Approve' buttons
 - the list of valid possible superiors, but with the requestor's choice selected

Implementing the approval process

To implement the approval process:

- 1. Select the attributes that requestors can modify.
- 2. Assign users to be requestors or approvers.
- 3. Create and modify the appropriate templates.

These steps are discussed below.

1. Select the attributes that requestors can modify

To specify the attributes that can be modified by requestors, perform the following ViewDS Management Agent help topic: *Select the attributes that requestors can modify*.

2. Assign users to be requestors or approvers

Users are assigned as requestors or approvers through either Basic Access Control or ViewDS Access Control.

If you are using Basic Access Control

Allocate the following access rights (see the ViewDS Management Agent help topic View or modify an Access Control Item):

- Requestors should have modify access to the operational attribute viewDSUpdateRequest, but not to the attributes available for modification.
- Approvers should have modify access to the operational attribute <code>viewDSUpdateRequest</code> and also to the attributes available for modification.

If you are using ViewDS Access Control

Allocate the following access rights (see the ViewDS Management Agent help topic Set the ViewDS Access Control for an entry):

- Requestors should have the <code>accessLevel</code> of requestor.
- Approvers should have the accessLevel of updater, admin or superuser.

3. Create and modify the appropriate templates

Make the following changes:

- Add the <u>Approval process tags</u> to the Expanded Entry page.
- Add an <u>InputChecked</u> directive to the format file.
- Create a <u>Request Remove Entry</u> page and add the configuration-file parameter <u>webRequestRemoveEntryTemplate</u>.

Configuring for two-factor authentication

Two-factor authentication is an approach to security that requires a user to enter two different types of authentication to prove their identity.

The user enters their regular username and password, and is then asked to enter an authentication code. The authentication code is a time-based one-time password (TBOP) generated by a third-party app (for example, Google Authenticate). As its name suggests, as soon as a one-time password enables access to Access Presence, it is no longer valid.

Use case

When two-factor authentication has been implemented, a user has the option to enable the feature on their account.

The user experience is as follows. The user:

- 1. Logs onto Access Presence with their username and password.
- 2. Clicks the menu option to **Enable two-factor authentication**. The resulting page provides an 'authentication secret' to the user.
- 3. Opens a third-party authenticator app (for example, Google Authenticate) and enters the 'authentication secret'. The app provides the user with a time-based one-time password (TOTP) that is valid for a limited period.
- 4. Returns to the Enable Two-factor Authentication page in Access Presence and submits the TOTP. Two-factor authentication is now enabled for the user's account.

The next time the user logs onto Access Presence, they enter their username and password as usual. However, they will then be presented with the Two-Factor Authentication page and required to enter a new TOTP.

The user also has the option to disable two-factor authentication on their account.

Implementing

To implement two-factor authentication so that the feature is available to Access Presence users:

- 1. Define a user attribute that will be used to store a user's authenticator secret.
- 2. In the ViewDS <u>configuration file</u>, set the value of the webSessionAuthenticator parameter to the name of the new user attribute.
- 3. Apply access controls to the new user attribute in order to:
 - Ensure that the value is only visible to the user and administrator.
 - Optionally allow applications to determine whether the attribute is present (without revealing the value) and therefore whether a user has enabled two-factor authentication on their account.
- 4. Make the new user attribute available to the account used for managing session-state information.
- 5. Define the following templates:
 - Enable Two-Factor Authentication template
 - Disable Two-Factor Authentication template
 - Two-Factor Authentication template
- 6. Add menu items to Access Presence so that users can access the pages to enable and disable <u>two-factor authentication</u>.
- 7. Declare the location of the templates in the ViewDS configuration file.

Free TOTP applications

The following is a selection of the free TOTP applications available:

- <u>Microsoft Authenticator</u>
- Google Authenticator: <u>Android</u> and <u>Apple</u>
- FreeOTP: <u>Android</u> and <u>Apple</u>